```
YYY
YYY
YYY
YYY
YYY
                      777
                                                   $$$$$$$$$$
$$$$$$$$$$
$$$$$$$$$$
```

Ps

YZ

ZS

ZS

78

78

ZS

28

ZS

ZS


ZS

ZS

ZS

ZS

LLLLLLLLL



PAR VO4

RR RR RR

RR RR

PARAMETER Table of contents	- PARAMETER DESCRIPTORS FOR SYSPARAM	16-SEP-1984 00:45:38	VAX/VMS Macro V04-00	Page
(1) 397 (1) 714 (1) 728 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952 (1) 3952	DECLARATIONS SYSTEM TIME VARIABLES SYSGEN PARAMETERS CONTROL PARAMETERS SYSTEM MESSAGE PARAMETERS SYSTEM LOADABLE CODE PARAMETERS TERMINAL DRIVER SYSTEM PARAMETERS RMS DEFAULT PARAMETERS PROCESS QUOTA DEFAULTS AND MINIMA FILE ACP CONFIGURATION DATA Job Controller Parameters Login Security Parameters Cluster Parameters Cluster Parameters COMPUTED VALUES MMG\$GL_PGDCOD Boundary of pageable exec			

PARAMETER V04-000 - PARAMETER DESCRIPTORS FOR SYSPARAM

16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-MAR-1980 00:52:39 [SYS.SRC]PRMSW.MAR;1

age 1

PAR VO4

00000001 0000

PRMSW=1

; SET SWITCH TO GENERATE PARAMETER DESCRIPTO

\* \* \* \* \*

11222222222223333333333333344

46

44555555555

PAR VO4

NOTICE !!!

\$SYIDEF IN MASD\$:<VMSLIB.SRC>STARDEFQZ.SDL MUST BE UPDATED WHEN ADDING PARAMETERS - BUT NOT WHEN DELETING PARAMETERS. \$SYIDEF CONTAINS THE PUBLIC DEFINITIONS OF THE \$GETSYI ITEM-CODES, AND EACH SYSGEN PARAMETER IS AUTOMATICALLY TRANSFORMED INTO A \$GETSYI ITEM. SYITABLE.MAR DEFINES \$GETSYI ITEMS WHICH ARE -NOT- SYSGEN PARAMETERS, AND SHOULD NOT BE MODIFIED WHEN ADDING OR SUBTRACTING SYSGEN PARAMETERS.

.IF DEFINED GETSYISW
.TITLE GETSYI - DEFINE SYSTEM PARAMETERS FOR GETSYI
.IF FALSE
.IF NDF, PRMSW
.TITLE SYSPARAM - SYSTEM PARAMETERS
.IFF
.TITLE PARAMETER - PARAMETER DESCRIPTORS FOR SYSPARAM
.ENDC
.ENDC

COPYRIGHT (c) 1978, 1980, 1982, 1984 BY DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS. ALL RIGHTS RESERVED.

THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY TRANSFERRED.

THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT CORPORATION.

DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.

FACILITY: EXECUTIVE DATA BASE

.IDENT 'V04-000'

ABSTRACT:

SYSPARAM CONTAINS THE EXECUTIVE CONTROL PARAMETERS AND CERTAIN KEY VARIABLES.

**ENVIRONMENT:** 

PAR

```
AUTHOR: R. I. HUSTVEDT, CREATION DATE: 09-0CT-1977
        MODIFIED BY:
                             DWT0238 David W. Thiel 24-Aug-1984 Change default value of QDSKINTERVAL to 20 seconds.
                 V03-080 DWT0238
                 V03-079 MIR0470
                             MIR0470 Michael I. Rosenblum 13-A
make tty_defport a specail sysgen parameter
                                                                                          13-Aug-1984
                 V03-078 CDS0004
                                                      Christian D. Saether
                                                                                          06-Aug-1984
                             Fix bug initializing exe$gl_static_flags introduced by cds0003.
                             WMC0075 Wayne Cardoza
Make SRP default 96.
                 V03-077 WMC0075
                                                                                          06-Aug-1984
                 V03-076 WMC0074
                             WMC0074 Wayne Cardoza Raise minimum working set parameters.
                                                                                          30-Jul-1984
                 V03-075 DWT0231
                                                      David W. Thiel
                                                                                          25-Jul-1984
                              Raise RECNXINTERVAL to 60 seconds.
                 V03-074 DWT0230
                             DWT0230 David W. Thiel 25-Jul-1984
Raise RECNXINTERVAL to 20. Make QDSKINTERVAL non-dynamic.
                 V03-073 WMC0073
                             WMC0073 Wayne Cardoza Raise max VIRTUALPAGECNT.
                                                                                          23-Jul-1984
                 V03-072 BLS0334 Benn Schreiber 23-JUL-1984 Raise default ENQLM, ASTLM, DIOLM and BIOLM parameters.
                             WHM0004 Bill Matthews 23-Jul-1984 Added a work station flag longword and defined the parameter WS_OPAO. Made LGI_BRK_TERM default to true. Raised paging file quota minimum from 256 to 512.
                 V03-071 WHM0004
                             CDS0003 Christian D. Saether 20-Jul-1984 Add one more buffer pool, ACP_DINDXCACHE, to file system caches. Add ACP_REBLDSYSD flag.
                 V03-070 CDS0003
                 V03-069 ACG0436 Andrew C. Goldstein, 12-Jul-1
Add LGI_BRK_TERM and LGI_BRK_DISUSER parameters
                                                                                          12-Jul-1984 11:50
                 V03-069 CDS0002
                             CDS0002 Christian D. Saether Raise minimum ACP_HDRCACHE to 3. Change default for ACP_MULTIPLE to 0.
                                                                                          11-July-1984
                 V03-068 JEJ0047
                             JEJ0047 J E Johnson 06-Jul-
Change RMS_GBLBUFQUO to be a dynamic parameter.
                                                                                          06-Jul-1984
                             WMC0067 Wayne Cardoza
Fix PQL minimum working set parameters.
Raise PHYSICALPAGES limits.
                                                                                          06-Jun-1984
                 V03-066 HWS0069
                                                     Harold Schultz
                                                                                          24-May-1984
```

21-Sep-1983 16:25

PAR VO4

```
0000
0000
0000
         177345671778901234567890123
                                      Added new type for LGI_ parameters.
                          V03-051 TMK0002
                                                            Todd M. Katz
                                      Add the special parameters PE1, PE2, PE3, PE4, PE5, PE6 for use
                                      by the PEDRIVER.
Add the SCS parameter PAPORTPOLL. If this boolean parameter is
                                      set the local CI port(s) will poll remote ports. If it isn't it
                                      won't.
                                     Change the following SYSGEN parameters' DEFAULT, MAX, MIN etc...
                                     1. Change the DEFAULT of MAXBUF from 1568 to 1584.
2. Change the DEFAULT of SCSSYSTEMID from 1 to 0.
3. Change the MIN of PAMAXPORT from -1 to 0.
4. Change the MAX of PAMAXPORT from -1 to 223.
                                     5. Change the ADDRESS of PAMAXPORT from SCS$GW_PAMXPORT to SCS$GB_PAMXPORT.
                                     6. Change the size of PAMAXPORT from WORD to BYTE.
0000
                          V03-050 WMC0048
                                                            Wayne Cardoza
                                                                                              16-Jan-1984
ŎŎŎŎ
                                      CJF related parameters must be made SPECIAL and defaulted
         194
0000
0000
0000
                          V03-049 JLV0328
                                                            Jake VanNoy
                                                                                              11-JAN-1984
0000
         197
                                      Add TTY_TIMEOUT and TTY_AUTOCHAR.
0000
         198
0000
         199
                          V03-048 KTA3097
                                                            Kerbey T. Altmann
                                                                                              10-Jan-1984
0000
                                      Set date to 1984.
0000
0000
                          V03-047 WMC0047
                                                                                              19-Dec-1983
                                                            Wayne Cardoza
0000
                                      WSMAX max is 64000 not 65280.
0000
                                      Make MMG$GW_BIGPFN a new cell.
0000
0000
                          V03-046 LMP0177
                                                                                              7-Dec-1983 11:32
                                                            L. Mark Pilant,
0000
                                     Add a dymanic parameter to control whether or not non-discretionary classification checks are to be performed.
0000
ÖÖÖÖ
V03-045 SSA0003
                                                            Stan Amway
                                     Added DORMANTWAIT to support outswap scheduling changes. Changed units and default for LONGWAIT.
                                                            David W. Thiel
                          V03-044 DWT0150
                                                                                              18-Nov-1983
                                      Add LOCKDIRWT and QDSKVOTES parameters. Deleted old
                                     VAXCLUSTER bit and define new VAXLCUSTER as a byte.
Reorder cluster parameters. Make ALLOCLASS non-dynamic.
Change PAPOLLINTERVAL default from 15 to 5 seconds.
Change SCSMAXMSG default from 96 to 112.
Change SRPSIZE default from 96 to 128 to close hole
                                      between SRP and IRP allocation pending a more complete
                                      examination of pool allocation.
                                     TMK0001 Todd M. Katz 12-Oct-1983
Add PQL_DJTQUOTA and PQL_MJTQUOTA - the default and minimum
byte creation quotas for job-wide logical name tables.
                          V03-043 TMK0001
```

Andrew C. Goldstein,

V03-042 ACG0360

PARA

V04-

```
Change defaults for LGI_xxx breakin parameters
                                     ACG0350 Andrew C. Goldstein, 19-Aug-1983 17:56 Raise MAXBUF minimum to 1200 to allow BACKUP to work
                          V03-041 ACG0350
                          V03-040 GAS0162 Gerry Smith 30-Jul-1983 Add LGI_PWD_TMO, the system password drop dead time.
                                     NPK3030 N. Kronenberg Change PAMAXPORT maximum from 223 to -1.
                          V03-039 NPK3030
                                                                                              29-Jul-1983
                                     RAS0179 Ron Schaefer 29-
Delete LOGPHASHTBL,LOGGHASHTBL,LOGSHASHTBL.
Change default of IMGIOCNT from 32 to 64.
Change default of RMS_EXTEND from 80 to 0.
                          V03-038 RAS0179
                                                                                               29-Jul-1983
                                     KFH0004 Ken Henderson 28
Add MAXQUEPRI, DEFQUEPRI, QDSKINTERVAL
Remove JOBQUEUES, REINITQUE, MAXPRINTSYMB
Change VMS_CLUSTER to VAXCLUSTER
                          V03-037 KFH0004
                                                                                              28 Jul 1983
0000
                                     Modify default of RECNXINTERVAL from 3 to 10
0000
0000
                          V03-036 NPK3029
                                      NPK3029 N. Kronenberg 26-Jul-1983
Tune up the SCS and PA parameters. Remove PASTRETRY.
0000
0000
                                      Add PAMXPORT, PASANITY.
0000
0000
                          V03-035 MSH0002
                                                            Maryann Hinden
                                                                                              08-Jul-1983
         256
257
258
259
260
261
263
0000
                                     Add cluster quorum disk parameters.
0000
0000
                          V03-034 GAS0142
                                                            Gerry Smith
                                                                                              20-Jun-1983
0000
                                     Add the login security parameters.
                                     PCA1015 Paul C. Anagnostopoulos 13-Jun-1983 Fix the valid ranges for the STARTUP_Pn parameters.
                          V03-033 PCA1015
                          V03-032 TCM0002
                                                            Trudy C. Matthews
                                                                                              1-Jun-1983
                                     Add ALLOCLASS parameter, a cluster parameter that defines the device allocation class for this system.
                          V03-031 SRB0086
                                                                                              24-May-1983
                                                            Steve Beckhardt
                                     Made LOCKIDTBL_MAX dynamic.
                          V03-030 JSV0295
                                                            Joost Verhofstad
                                                                                              20-MAY-1983
                                     Add SYSGEN parameters CJFLOAD and CJFSYSRUJ
                          V03-029 KFH0003
                                                            Ken Henderson
                                                                                              20 May 1983
                                     Increased default values:
SPTREQ 720 -> 896
GBLPAGES 3072 -> 4096
                                                            80 -> 128
                                     GBLSECTIONS
                          V03-028 KDM0044
                                                                                              03-May-1983
                                                            Kathleen D. Morse
                                     Add EXESGL_ARCHFLAG.
                                     PCA1015 Paul C. Anagnostopoulos 28-Apr-1983
Add TAILORED parameter to specify whether or not this system
                          V03-027 PCA1015
                                     is tailored (has a library disk).
```

0000	286 : 287 :		Add STARTUP Pn parameters for passing in system startup procedure.	formation to the
0000	289	v03-026	SRB0081 Steve Beckhardt Added new parameter LOCKIDTBL_MAX.	28-Apr-1983
0000 0000 0000 0000 0000 0000 0000 0000 0000	292 293 294	v03-025	RNG0025 Rod Gamache Change default value of MAXBUF to be mor for the DEUNA device driver.	21-Apr-1983 e flexible
0000	296 297 298	v03-024	KFH0002 Ken Henderson Modify call to SYI_ITEM_CODE to support Ascii sysnodename.	14 Apr 1983
0000	300 301	v03-023	MIR0030 Michael I. Rosenblunm Make line editing the default	14-Apr-1983
0000	303 :	v03-022	TCM0001 Trudy C. Matthews Allow WSMAX to grow to 65280.	8-Apr-1983
0000	306 307	v03-021	MSH0001 Maryann Hinden Add ASCII type. Correct default for SCS	25-Mar-1983 NODEH.
0000 0000 0000 0000 0000 0000 0000 0000 0000	309 : 310 : 311 :	v03-020	DWT0080 David W. Thiel Define cluster class of parameters contaguorum, VOTES, and CNXRETRYINT.	1-Mar-1983 ining
0000	313	v03-019	JWH0191 Jeffrey W. Horn Change default value for PIOPAGES.	28-Feb-1983
0000 0000 0000 0000 0000 0000 0000	316 317 318 319 320 321 322 323 325	v03-018	Add STARTUP Pn parameters for passing in system startup procedure.  SRB0081 Steve Beckhardt Added new parameter LOCKIDTBL_MAX.  RNG0025 Rod Gamache Change default value of MAXBUF to be more for the DEUNA device driver.  KFH0002 Ken Henderson Modify call to SYI_ITEM_CODE to support Ascii sysnodename.  MIR0030 Michael I. Rosenblunm Make line editing the default  TCM0001 Trudy C. Matthews Allow WSMAX to grow to 65280.  MSH0001 Maryann Hinden Add ASCII type. Correct default for SCS DWT0080 David W. Thiel Define cluster class of parameters contaguorum, VOTES, and CNXRETRYINT.  JWH0191 Jeffrey W. Horn Change default value for PIOPAGES.  KFH0001 Ken Henderson Added conditionals for GETSYISW, to let this file be used to define the sysboot parameters for SYS\$GETSYI/F\$GETSYI/LIB\$GETSYI/LIB\$GETSYI/F\$GETSYI/LIB\$GETSYI/F\$GETSYI/LIB\$GETSYISW IS DEFINED.	15 Feb 1983 SETSYI SE THAT ALL SLIZED TO NOT
0000	325 326 327	v03-017	RNG0017 Rod N. Gamache Change default value for PHYSICALPAGES.	11-Feb-1983
0000 0000 0000 0000 0000	329 330 331 332 333	v03-016	DWT0071 David W. Thiel Add VMS_CLUSTER parameter and correspond LOADCLUSTR bit in SGN\$GL_LOADFLAGS. Add PRCPOLINTERVAL parameter with global SCS\$GW_PRCPOLINT.	28-Jan-1983 ing name
0000 0000 0000 0000 0000 0000	335 336 337 338	v03-015	STJ3053 Steven T. Jeffreys Added LOADERAPAT and LOADCHKPRT paramete SGN\$GL_LOADFLAGS, a system global longwo the loading of various pieces of the EXE	21-Jan-1983 rs, and defined rd to control C.
0000	336 : 337 : 338 : 340 : 341 : 342 :	v03-014	KTA3029 Kerbey T. Altmann Set date to 1983.	11-Jan-1983

```
SRB0057 Steve Beckhardt 16-Dec-1982 Increased maximum size of LOCKIDTBL to 65535.
                          V03-013 SRB0057
                          V03-012 DMW4016
                                                            DMWalp
                                                                                               15-Dec-1982
                                      Added parameters for size of new logical name hash tables
                                      JWH0117 Jeffrey W. Horn 29
Add PIOPAGES CTLPAGES, and CTLIMGLIM.
Change maximum of PHYSICALPAGES to 65536.
Change default of SCSSYSTEMIDH to 0.
                          V03-011 JWH0117
                                                                                               29-0ct-1982
V03-010 KTA3016
                                                            Kerbey T. Altmann
                                                                                               21-0ct-1982
                                      Add SCSNODENAME.
                          V03-009 HRJ0064
                                                            Herb Jacobs
                                                                                               21-Apr-1982
                                      Fix default values of RMS_DFMBC, RMS_EXTEND, MPW_LOLIMIT.
                                                                                               15-Apr-1982
                          V03-008 JLV0208
                                                             Jake Vannoy
                                      Fix default values for TTY_SILOTIME, WSINC, WSDEC.
                          V03-007 JLV0207
                                      JLV0207 Jake VanNoy 5-APR-1982
Add some smarts to PARAMETER macro to ignore dynamic
                                      bits if they are not in EXESGL_DEFFLAGS. This prevents the dynamic bits in STJ0249 from being included in
                                      PRMSM_DYNFLAGS.
                          V03-006 STJ0249
                                                            Steven T. Jeffreys
                                                                                               01-Apr-1982
                                      Add global longword for system message flags. Define EXESV_MOUNTMSG and EXESV_DISMOUMSG to control operator
                                      notification of mounts and dismounts, respectively. By default, both are disabled.
                          V03-005 MLJ0085
                                      MLJ0085 Martin L. Jack 01-Apr-1982 Add EXE$V_JOBQUEUES, EXE$V_REINITQUE to control initialization of JBCSYSQUE by job controller.
                                      PHLOG41 Peter H. Lipman 0 Default setting for SAVEDUMP must be off.
                          V03-004 PHL0041
                                                                                               01-Apr-1982
                          V03-003 HRJ0061
                                                                                               28-Mar-1982
                                                             Herb Jacobs
                                      Fix categories for /MAJOR, /SYS, /SYSGEN, correct
                                      some default values, and change global name of SWPFILCNT.
                                     PHL0040 Peter H. Lipman 22-Mar-1982 Add EXE$V_PAGFILDMP, EXE$V_SAVEDUMP, EXE$GW_PGFL_FID to support the dump file in the page file.
                          V03-002 PHL0040
ŎŎŎŎ
0000
          390
                          V03-001 JLV0193
                                                                                               15-MAR-1982
                                                             Jake VanNoy
                                      Add TTY_SILOTIME. Change defaults for TTY_DWNER and TTY_PROT and PQL_ENQLM. Change names of TTYSCANDELTA to TTY_SCANDELTA
0000
0000
0000
                                      and DIACTYPE to TTY DIALTYPE.
         394
395
0000
```

PARI VO4-

```
.SBTTL DECLARATIONS
            399012340567890111
                      INCLUDE FILES:
DEFINE SYSSGETSYL ITEM CODES
DEFINE QUOTA LIST CODES
DEFINE PARAMETER DESCRIPTOR
                                  $SYIDEF
                                  SPQLDEF
                                  SPRMDEF
                                                                                              SYSGEN CONSTANTS
DEFINE TERMINAL CHARACTERISTICS
DEFINE MORE TERMINAL DEFINITIONS
                                  $SGNDEF
                                  STIDEF
                                  STT2DEF
                       MACRO TO GENERATE PARAMETER DESCRIPTOR IF PRMSW IS TRUE OTHERWISE
                       SIMPLY DEFINE PARAMETERS
                       MACROS:
                                               PFNALC SIZ, SYMLST
SYM, <SYMLST>
PFN$A'SIZ'_'SYM
                                   .MACRO
                                  . IRP
                                  DEFINE
                                   .ENDR
                                                LONG
                                   . ALIGN
                                   . LONG
                                   . ENDM
                                                PFNALC
                                   .MACRO
                                                PARAMETER, ADDRESS, NAME, TYPE=STATIC, DEFAULT=0, MIN=-1, MAX=-1,-
                                                UNIT, SIZE=LONG, BIT
                      When GETSYISW is defined, the macro PARAMETER becomes a conduit to a lower level macro SYI_ITEM_CODE. In the fashion of JPI_ITEM_CODE and DVI_ITEM_CODE, SYI_ITEM_CODE is called multiple times (once per item) by the larger macro SYI_GENERATE_TABLE. This file becomes the definition of SYI_GENERATE_TABLE when GETSYISW is defined.
                                  OUTLEN = 4
                                                IDENTICAL <SIZE><BYTE>, OUTLEN = 1
IDENTICAL <SIZE><WORD>, OUTLEN = 2
IDENTICAL <SIZE><LONG>, OUTLEN = 4
IDENTICAL <SIZE><QUAD>, OUTLEN = 8
IDENTICAL <SIZE><OCTA>, OUTLEN = 16
            IIF
                                  . IF
                                                DEFINED GETSYISW
                                                BLANK BIT
                                   . IF
                                  . IF
                                                NOT DEFINED SYIS 'NAME
SYIS 'NAME SHOULD BE DEFINED IN STARDEFQZ.SDL (EXE-SECT)
                                  .WARN ;
                                   .ENDC
                                  . IF
                                                 IDENTICAL <UNIT> <Ascii>
                                                               EXE,-
                                                                                               TABLE BASE - EXEC CELLS
                                  SYI_ITEM_CODE
                                                               <ADDRESS> .-
                                                                                               SOURCE
```

16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1 PAR

V04

(1)

- PARAMETER DESCRIPTORS FOR SYSPARAM DECLARATIONS

```
- PARAMETER DESCRIPTORS FOR SYSPARAM DECLARATIONS
                                               16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                              PADSTR .-
                                                                  DTYPE = PADDED STRING
             BITPOS
                                              PRMSC 'SIZE',-
                                                                : OUTLEN
                           . IF_FALSE
      ŎŎŎŎ
     0000
0000
                                                                  TABLE BASE - EXEC CELLS
                           SYI_ITEM_CODE
                                              EXE .-
                                              <NAME> .-
                                              <ADDRESS>,-
                                                                  SOURCE
                                                                  DTYPE = DECIMAL NUMBER
                                              DECNUM, -
                                                                  BITPOS
                                              PRMSC_'SIZE',-
                                                                  BITSIZ
                                              OUTLEN
                                                                : OUTLEN
                            .ENDC
                                              : IDENTICAL <UNIT><Ascii>
     . IF_FALSE
                                              : BLANK BIT
                           . IF NOT DEFINED SYIS NAME . WARN ; SYIS NAME SHOULD BE DEFINED IN STARDEFQZ.SDL (FLD-SECT)
                           SYI_ITEM_CODE
                                              FLD,-
                                                                : TABLE BASE - FIELD DATA
                                              <NAME>,-
                                              <ADDRESS> .-
                                              BITVAL, -
                                              <BIT>,-
                           .ENDC
                                              ; BLANK BIT
                           . IF_FALSE
                                             : DEFINED GETSYISW
                           . IF
                                    DF , PRMSW
                                                                  DO IF CREATING PARAMETER DESCRIPTOR
                  PRMSAV
                                                                  SAVE LOC COUNTER
                            PSECT $$$918,LONG
                                                                  SET BASE FOR THIS DESCRIPTOR GENERATE SPACE
                           BAS...=.
                            BLKB PRMSC_LENGTH
                           SAV ... = .
                           PRM
                                       ADDR
                           LONG
PRM
                                     ADDRESS
                                     L_DEFAULT
                                     DEFAULT
                           LONG
PRM
                                    L MIN
                           .LONG
                                    L MAX
                            LONG
                                    GREATER
                                                       <%LENGTH(NAME)-PRMSC_MAXNAMLEN>
                           .ERROR
.ENDC
PRM
                                     ; The parameter called NAME has too many characters
                                    T NAME '%
                            .ASCIC
                                     GREATER
                                                       <%LENGTH(UNIT)-PRMSC_MAXUNILEN>
                                    ; The quantity called UNIT has too many characters
```

ENDC

PARAMETER V04-000

- PARAMETER DESCRIPTORS	FOR	SYSPARAM	
-------------------------	-----	----------	--

16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1

```
T_UNIT
%*UNIT'%
B_SIZE
B_BIT
PRM$C_'SIZE
               ASCIC
PRM
.IF
                                                            SET FIELD SIZE
               BYTE
BYTE
PRM
                          B POS
               .BYTE
.ENDC
PRM
                          L_FLAGS
               TYP...=0
.IRP TYPNAM, <TYPE>
TYP...=TYP...!PRM$M_'TYPNAM
               .IF NB BIT
.IF EQ PRMSM 'TYPNAM-PRMSM DYNAMIC
.IF IDN ADDRESS, EXESGL DEFFLAGS
PRMSM_DYNFLAGS == PRMSM_DYNFLAGS!<1abit>
                                                           DEFINE PRMSM_DYNFLAGS
               .ENDC
.ENDC
                .ENDR
                        TYP...
               .LONG
                                                             REPOSITION LOCATION COUNTER
                .PSECT $$$917A,PAGE
                                                            BACK TO NORMAL PSECT
                                                            RESTORE LOCATION COUNTER
                .=PRMSAV...
                          B,BIT
GT,OUTLEN-4
                                                            IF LENGTH >4 FORCE LONGWORD ALIGNMENT
                ALIGN LONG
               .ALIGN
                         'SIZE'
     ADDRESS'::
                                                            DEFINE GLOBAL VALUE
               .ENDC
                          B,BIT
                          GT, OUTLEN-4
                                                            IF LENGTH >4 FORCE LONGWORD ALIGNMENT
                .ALIGN
                         LONG
                .LONG
                          DEFAULT
                                                            GENERATE DEFAULT QUAD VALUE
                . LONG
                          DEFAULT
                          GT, OUTLEN-8
                          DEFAULT
DEFAULT
                . LONG
                                                            GENERATE DEFAULT OCTA VALUE
55589
55555561
55645
55667
                LONG
                ENDC
                . IFF
               .ALIGN 'SIZE'
                                                            GENERATE DEFAULT VALUE
               .ENDC
               .ENDC
                                    : DEFINED GETSYISW
               .ENDM
                          PARAMETER
```

PGFLCRIT,-TBCHK,-PAGFILDMP .-

PARAMETER V04-000		SYST	RAMETER TEM TIME	DESCRIPTORS VARIABLES	FOR SYS	PARAM 16-SEP-1984 00 5-SEP-1984 03	0:45:38 3:55:49	VAX/VMS Macro V04-00 [SYS.SRC]SYSPARAM.MAR;1	Page	15
		0000		714 715 :	.SBTTL	SYSTEM TIME VARIABLES				
		8	0000	716		SYSTEM TIME VARIABLES				
	00804737	66070000	0000 0000 0000 0000 0000	718 719 720 ·	DEFINE .QUAD	*X008C473766070000	: TIME	OF DAY CLOCK BASE (BOOT 1	IME)	
		10000000	0008 720; 0008 721 0008 722 0000 723 0000 724 0000 725 0000 726	DEFINE .LONG	EXESGL_TODR	: TIME : TO E : BECA : IS U	OF DAY REGISTER VALUE COR XE\$GQ_TODCBASE; IT'S NOT 2 NUSE ANYTHING LESS THAN 102 USED TO INDICATE CLOCK LOST	RESPOND I	NG	
			0000	726	.ENDC	; NOT_DEFINED GETSYISW				

NUMBER OF KNOWN FILE LISTS - ESTABLISHES THE MAXIMUM NUMBER OF KNOWN

PAR VO4

Page

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                           16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                    Page
                                   FILE LISTS THAT CAN BE MADE KNOWN TO THE SYSTEM.
                 785678890127995799890
                                   PARAMETER
                                                          ADDRESS=SGN$GB_KFILSTCT,-
                                                          DEFAULT=4,-
MIN=2,-
MAX=255,-
       000C
000C
                                                          NAME=KFILSTONT,-
SIZE=BYTE,-
                                                          TYPE=<SYSGEN,SYS>,-
       ÖÖÖČ
                                                          UNIT=Slots
       OOOC
                                   .IIF
                                              NOT_DEFINED GETSYISW, .ALIGN WORD
                          GLOBAL SECTION COUNT - DETERMINES THE MAXIMUM NUMBER OF GLOBAL SECTIONS WHICH CAN BE MADE KNOWN TO THE SYSTEM BY ALLOCATING THE NECESSARY STORAGE FOR THE GST ENTRIES.
                 801
                                                          ADDRESS=SGN$GW_GBLSECNT,-
DEFAULT=128,-
MIN=20,-
                                   PARAMETER
                                                          NAME=GBLSECTIONS,-
                                                          SIZE=WORD,-
                                                          TYPE=<SYSGEN, SYS, MAJOR>,-
                                                          UNIT=Sections
                 809
                 810
811
812
813
814
                          GLOBAL PAGE COUNT - ESTABLISHES THE SIZE OF THE GLOBAL PAGE TABLE AND THE LIMIT FOR THE TOTAL NUMBER OF GLOBAL PAGES THAT CAN BE CREATED.
                                                          ADDRESS=SGN$GL_MAXGPGCT,-
                                   PARAMETER
                                                          DEFAULT=4096,-
                                                          NAME=GBLPAGES .-
                                                          SIZE=LONG.-
                                                          TYPE=<SYSGEN, SYS, MAJOR>,-
                                                          UNIT=Pages
                          GLOBAL PAGE PAGE FILE PAGE LIMIT - ESTABLISHES THE MAXIMUM NUMBER OF GLOBAL PAGES WITH PAGE FILE BACKING STORE THAT CAN BE CREATED.
                                                          ADDRESS=SGN$GL_GBLPAGFIL,-
                                   PARAMETER
                                                         DEFAULT=1024,-
MIN=128,-
                                                          NAME=GBLPAGFIL .-
                                                          SIZE=LONG,-
                                                          TYPE=<SYS>,-
                                                          UNIT=Pages
                          MAXIMUM PROCESS COUNT - DETERMINES THE MAXIMUM NUMBER OF PROCESSES
                                                         ADDRESS=SGN$GW_MAXPRCCT,-
DEFAULT=72,-
MIN=12,-
MAX=8192,-
                                   PARAMETER
                                                          NAME = MAXPROCESSCNT, -
```

PAR

V04

(1)

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                          16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                 Page
                                                         SIZE=WORD,-
TYPE=<SYSGEN,SYS,MAJOR>,-
       UNIT=Processes
                          PROCESS SCAN COUNT - DETERMINES THE MAXIMUM NUMBER OF PROCESSES TO SCAN
                          FOR PRIORITY BOOSTING.
                                  PARAMETER
                                                         ADDRESS=SGN$GW_PIXSCAN,-:
DEFAULT=1,-
                                                         MIN=0,-
MAX=8192
                                                         NAME=PIXSCAN,-
SIZE=WORD,-
                                                         TYPE=<SPECIAL, DYNAMIC>,-;
                                                         UNIT=Processes
                         PROCESS SECTION COUNT - GUARANTEED NUMBER OF PROCESS SECTIONS THAT CAN BE CREATED. DEPENDING ON SIZE OF WORKING SET, THE ACTUAL NUMBER OF SECTIONS CAN ACTUALLY BE GREATER.
                  860
                 861
862
863
864
866
867
871
872
873
                                                         ADDRESS=SGN$GW_MAXPSTCT,-
DEFAULT=32,-
                                  PARAMETER
        0000
        ÖÖÖC
                                                         MIN=5,-
       000C
000C
000C
                                                         MAX=1024
                                                         NAME=PROCSECTONT,-
                                                         SIZE=WORD .-
                                                         TYPE=<SYSGEN,SYS>,-
       0000C
                                                         UNIT=Sections
                         MINIMUM WORKING SET SIZE - ESTABLISHES THE SMALLEST SIZE THAT ADJWSL WILL
                                  SET A PROCESS' WORKING SET.
                                  PARAMETER
                                                         ADDRESS=SGN$GW_MINWSCNT,-
                                                         DEFAULT=20,-
                                                         MIN=10,-
                 888888888889912345678
88888888889999999998
                                                         NAME = MINWSCNT . -
                                                         SIZE=WORD,-
                                                         TYPE=<STATIC,SYSGEN,SYS>,-
                                                         UNIT=Pages
                         NUMBER OF PAGING FILES - DETERMINES THE MAXIMUM NUMBER OF PAGING FILES
                                  THAT CAN BE MADE KNOW TO THE SYSTEM.
                                                         ADDRESS=SGN$GW_PAGFILCT,-
                                  PARAMETER
                                                         DEFAULT=2,-
                                                         MIN=1,-
                                                         MAX=63.-
                                                         NAME = PAGFILCHT, -
                                                         SIZE=WORD,-
                                                         TYPE=<SYS, SYSGEN>,-
        0000
                                                         UNIT=files
```

PAR

V04

Page

```
PARAMETER
V04-000
```

```
VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR;1
SYSGEN PARAMETERS
                     NUMBER OF SWAP FILES - ESTABLISHES THE MAXIMUM NUMBER OF SWAPFILES THAT
                            CAN BE MADE KNOWN TO THE SYSTEM.
                            PARAMETER
                                               ADDRESS=SGN$GW_SWPFILES,-
                                               DEFAULT=2,-
              906
907
908
909
                                               MIN=0,-
MAX=63,-
                                               NAME = SWPFILCHT, -
                                               SIZE=WORD,-
              910
911
912
913
914
915
916
917
918
                                               TYPE=<SYS, SYSGEN>,-
                                               UNIT=Files
                    SYSTEM WORKING SET COUNT - ESTABLISHES THE NUMBER OF PAGES FOR THE WORKING
                            SET CONTAINING THE CURRENTLY RESIDENT PAGES OF PAGABLE SYSTEM SPACE.
      0000
     0000
                            PARAMETER
                                               ADDRESS=SGN$GW_SYSDWSCT,-
     000C
                                               DEFAULT=250 .-
     000C
                                               MIN=40.-
                                               MAX=16384 .-
      0000
                                               NAME = SYSMWCNT . -
      0000
                                               SIZE=WORD .-
                                               TYPE=<SYSGEN,SYS,MAJOR>,-
      000C
      000C
                                               UNIT=Pages
      000C
      0000
     0000
                    INTERRUPT STACK SIZE - ESTABLISHES THE SIZE OF THE INTERRUPT STACK IN PAGES
      0000
     0000
                                               ADDRESS=SGN$GW_ISPPGCT,-
DEFAULT=2,-
                            PARAMETER
      0000
     0000
                                               MIN=1,-
      0000
                                               NAME=INTSTKPAGES .-
      0000
                                               SIZE=WORD .-
      000C
                                               TYPE=<SYS, SYSGEN>,-
      000C
                                               UNIT=Pages
      0000
      0000
                     AMOUNT OF EXTRA INTERRUPT STACK TO LEAVE WHEN DOING DEADLOCK SEARCH
      0000
                                              ADDRESS=LCK$GL_EXTRASTK,-
DEFAULT=512,-
MIN=256,-
      0000
                            PARAMETER
      000C
     000C
                                               NAME = DLCKEXTRASTK, -
      0000
                                               SIZE=LONG,-
      000C
                                               TYPE=<SPECIAL>,-
                                               UNIT=Bytes
              949
950
951
953
953
955
                     BALANCE SET COUNT - DETERMINES THE MAXIMUM NUMBER OF PROCESS THAT CAN BE
                            BE CONCURRENTLY RESIDENT.
                            PARAMETER
                                               ADDRESS=SGNSGL_BALSETCT,-
                                               DEFAULT=36,-
                                               MIN=4 -
MAX=1024,-
```

B 13

- PARAMETER DESCRIPTORS FOR SYSPARAM

```
PARAMETER
V04-000
```

```
20 (1)
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                                                            VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR:1
                                                                                                                                      Page
SYSGEN PARAMETERS
       NAME=BALSETCHT,-
                                                           SIZE=LONG,-
TYPE=<SYSGEN,SYS,MAJOR>,-
                                                           UNIT=Slots
                 960
961
963
963
965
                          COUNT OF PRE-ALLOCATED I/O PACKETS - DETERMINES THE NUMBER OF I/O PACKETS TO BE PRE-ALLOCATED AND LINKED TOGETHER FOR FAST ALLOCATION AND
                                   DEALLOCATION.
                                                           ADDRESS=SGN$GL_IRPCNT,-
                                   PARAMETER
                                                           DEFAULT=60,-
                                                           MIN=0,-
MAX=32768
                                                           NAME=IRPCOUNT,-
                                                          SIZE=LONG,-
TYPE=<SYSGEN, MAJOR, SYS>,-
                                                           UNIT=Packets
                          NUMBER OF PACKETS TO WHICH THE IRPLIST MAY BE EXTENDED.
       ÖÖÖC
       ŎŎŎĊ
                                                           ADDRESS=SGN$GL_IRPCNTV,-;
DEFAULT=1000,-
                                   PARAMETER
       ÖÖÖC
       ÖÖÖC
                                                           MIN=0,-
MAX=32768,
       OOOC
       0000
                                                           NAME=IRPCOUNTY,-
       ÖÖÖC
                  981
                                                           SIZE=LONG,-
TYPE=<SYSGEN,SYS>,-
                 982
983
       ÖÖÖC
       0000
                                                           UNIT=Packets
       0000
       000C
                  985
                          MAXIMUM SIZE OF PROCESS WORKING SET. DETERMINES THE SYSTEM WIDE MAXIMUM SIZE OF A PROCESS WORKING SET REGARDLESS OF PROCESS QUOTA.
                 986
987
       0000
       000C
000C
000C
                                                           ADDRESS=SGN$GL_MAXWSCNT,-
DEFAULT=1024,- ;
                                   PARAMETER
                 990
991
992
993
                                                           MIN=60,-
                                                           MAX=64000
                                                           NAME = WSMAX , -
                                                           SIZE=LONG .-
       0000
                                                           TYPE=<SYSGEN, SYS, MAJOR>,-
       0000
                                                           UNIT=Pages
                 996
997
998
999
       000C
                          NON-PAGED DYNAMIC POOL - DETERMINES THE NUMBER OF BYTES TO ALLOCATE FOR
                                   THE NON-PAGED DYNAMIC POOL.
                1000
                                                          ADDRESS=SGN$GL_NPAGEDYN,-
DEFAULT=131072,-
MIN=16384,-
                 00.
                                   PARAMETER
                 002
                                                                                                 256 pages
                 003
                 004
                                                           NAME=NPAGEDYN,-
                 005
                                                           SIZE=LONG,-
                                                           TYPE=<SYSGEN, SYS, MAJOR>,-
                 1006
1007
       0000
                                                           UNIT=Bytes
                1008
1009
1010
1011
1012
       0000
                          NON-PAGED DYNAMIC POOL - DETERMINES THE NUMBER OF BYTES TO WHICH THE NON-PAGED DYNAMIC POOL MAY BE EXTENDED. THIS PARAMETER IS USED TO ALLOCATE THE NECESSARY PAGE TABLE ENTRIES.
       000C
```

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                                                    VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                     21
                                                                                                                            Page
SYSGEN PARAMETERS
                                                      ADDRESS=SGN$GL_NPAGEVIR,-
DEFAULT=400000,-
MIN=16384,-
;
                                 PARAMETER
      1014
               1015
1016
1017
1018
1019
                                                       NAME = NPAGEVIR , -
                                                      SIZE=LONG,-
TYPE=<SYSGEN,SYS>,-
                                                      UNIT=Bytes
                        PAGED DYNAMIC POOL - DETERMINES THE NUMBER OF BYTES TO ALLOCATE FOR THE
                                 PAGED DYNAMIC POOL.
                                                      ADDRESS=SGN$GL_PAGEDYN,-
DEFAULT=190000,-
MIN=10240,-
                                 PARAMETER
                                                       NAME = PAGEDYN, -
                                                      SIZE=LONG,-
TYPE=<SYSGEN,SYS,MAJOR>,-
                                                       UNIT=Bytes
                        MAXIMUM VIRTUAL PAGE COUNT - DETERMINES THE TOTAL NUMBER OF PAGES THAT CAN BE MAPPED FOR A PROCESS, WHICH CAN BE DIVIDED IN ANY FASHION BETWEEN PO AND P1 SPACE.
                                                      ADDRESS=SGN$GL_MAXVPGCT,-
DEFAULT=8192,-
MIN=512,-
MAX=300000,-
                                 PARAMETER
                                                                                          MORE THAN 128 MEGABYTES
                                                       NAME = VIRTUAL PAGE CNT . -
       ÖÖÖC
                                                      SIZE=LONG,-
TYPE=<SYSGEN,SYS,MAJOR>,-
       0000
       ÖÖÖC
                                                      UNIT=Pages
       0000
               1046
1047
1048
       0000
       0000
                        REQUESTED SPT EXTENSION - NUMBER OF ADDITIONAL SPT SLOT TO ALLOW
       0000
       0000
                                                      ADDRESS=SGN$GL_SPTREQ,-
DEFAULT=896,-
                                 PARAMETER
      NAME=SPTREQ .-
                                                      SIZE=LONG.-
TYPE=<SYS,SYSGEN>,-
                                                      UNIT=Pages
                        EXTRA USER STACK AUTOMATICALLY PROVIDED BY THE IMAGE ACTIVATOR
                                 SO THAT THE OPERATING SYSTEM CAN RECOVER FROM A STACK OVERFLOW.
                                                      ADDRESS=SGN$GL_EXUSRSTK,-;
DEFAULT=<2*5125,-;
MIN=<2*512>,-;
                                 PARAMETER
                                                       NAME = EXUSRSTK, -
                                                       SIZE=LONG,-
               1064
1065
1066
1067
1068
1069
                                                       TYPE=<SPECIAL>
                                                       UNIT=<Pages*512>
                        NUMBER OF LARGE REQUEST PACKETS TO ALLOCATE TO THE LRP LOOK ASIDE LIST
                                 PARAMETER
                                                       ADDRESS=SGN$GL_LRPCNT,-;
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                        16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                                     VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                                            Page
                                                      DEFAULT=4,-
MIN=0,-
MAX=4096,-
      NAME=LRPCOUNT,-
SIZE=LONG,-
                                                       TYPE=<SYS, SYSGEN, MAJOR>,-
                                                       UNIT=<Packets>
               1078
1079
                        NUMBER OF LARGE REQUEST PACKETS TO WHICH THE LRP LOOK ASIDE LIST MAY BE EXTENDED. USED TO ALLOCATE THE APPROPRIATE VIRTUAL SPACE.
               1080
                                                      ADDRESS=SGN$GL_LRPCNTV,-;
DEFAULT=80,-
MIN=0,-
               1081
1082
1083
1084
1085
1086
1087
1088
1089
                                 PARAMETER
                                                       MAX=4096,
                                                       NAME=LRPCOUNTY,-
                                                       SIZE=LONG,-
                                                       TYPE=<SYS, SYSGEN>,-
                                                      UNIT=<Packets>
               1090
                        SIZE OF LARGE REQUEST PACKETS (BYTES)
               1092
                                                      ADDRESS=SGN$GL_LRPSIZE,-;
DEFAULT=576,-
MIN=256,-
MAX=16384,-
                                PARAMETER
               1094
               1095
               1096
1097
                                                       NAME=LRPSIZE,-
                                                       SIZE=LONG,-
               1098
                                                       TYPE=<SYS, SYSGEN>,-
               1099
                                                      UNIT=<Bytes>
               1100
               1101
                        MINIMUM ALLOCATION REQUEST FOR LARGE REQUEST PACKETS (BYTES)
               1102
      ADDRESS=SGN$GL_LRPMIN,-;
                                PARAMETER
                                                      DEFAULT=480,-
MIN=256,-
MAX=16384,-
               1104
               1105
               1106
                                                       NAME = LRPMIN, -
               1108
                                                       SIZE=LONG
               1109
                                                       TYPE=<SPECIAL>,-
               1110
                                                      UNIT=<Bytes>
               1111
               1112
1113
1114
1115
                        NUMBER OF SMALL REQUEST PACKETS TO ALLOCATE TO THE SRP LOOK ASIDE LIST
                                                      ADDRESS=SGN$GL_SRPCNT,-;
DEFAULT=120,-
MIN=0,-
                                 PARAMETER
               1116
                                                      MAX=4096.
               1117
               1118
                                                       NAME=SRPCOUNT,-
                                                       SIZE=LONG,-
               1119
               1120
1121
1122
1123
1124
1125
1126
                                                       TYPE=<SYS, SYSGEN, MAJOR>,-
                                                      UNIT=<Packets>
                        NUMBER OF SMALL REQUEST PACKETS TO WHICH THE SRP LOOK ASIDE LIST
                        MAY BE EXTENDED. USED TO ALLOCATE THE APPROPRIATE VIRTUAL SPACE.
                                 PARAMETER
                                                       ADDRESS=SGN$GL_SRPCNTV,-;
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                        16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                                      VAX/VMS Macro VO4-00
[SYS.SRC]SYSPARAM.MAR;1
                                                                                                                             Page
                                                       DEFAULT=1000,-
MIN=0,-
MAX=131072,-
                                                      NAME=SRPCOUNTV,-
SIZE=LONG,-
TYPE=<SYS,SYSGEN>,-
      UNIT=<Packets>
                        SIZE OF SMALL REQUEST PACKETS (BYTES)
                                                      ADDRESS=SGN$GL_SRPSIZE,-;
DEFAULT=96,-
MIN=96,-
MAX=144,-
                                 PARAMETER
                                                       NAME=SRPSIZE,-
SIZE=LONG,-
                                                       TYPE=<SPECIAL>,-
              1144
1145
1146
1147
1148
1149
1150
1151
1152
                                                       UNIT=<Bytes>
                        MINIMUM ALLOCATION REQUEST FOR SMALL REQUEST PACKETS (BYTES)
                                                      ADDRESS=SGN$GL_SRPMIN,-;
DEFAULT=32,-
MIN=0,-
MAX=144,-
                                 PARAMETER
                                                       NAME = SRPMIN, -
                                                       SIZE=LONG,-
               1154
1155
1156
1157
1158
1159
                                                       TYPE=<SPECIAL>,-
                                                       UNIT=<Bytes>
                                 PERMANENT I/O CHANNEL COUNT - SPECIFES THE NUMBER OF PERMANENT I/O
                                 CHANNELS TO PROVIDE.
                                                       ADDRESS=SGN$GW_PCHANCNT,-
               1160
                                 PARAMETER
                                                      DEFAULT=127,-
MIN=31,-
               1161
1162
1163
1164
1165
1166
1167
1168
1169
                                                       MAX=2047 .-
                                                       NAME = CHANNEL CNT, -
                                                       SIZE=WORD,-
                                                       TYPE=<SPECIAL>,-
                                                       UNIT=Channels
                                 PROCESS I/O PAGES - SPECIFIES THE NUMBER OF PAGES OF PROCESS
                                 I/O ADDRESS SPACE FOR PROSTRT TO CREATE.
               1171
               1172
                                                       ADDRESS=SGN$GW_PIOPAGES, - ;
                                 PARAMETER
                                                       DEFAULT=120,
MIN=10, -
               1174
                                                       NAME = PIOPAGES, -
               1176
1177
                                                       SIZE=WORD.
                                                       TYPE=<SPECIAL>, -
               1178
1179
1180
1181
1182
1183
                                                       UNIT=Pages
                                 CONTROL REGION IMPURE PAGES - SPECIFIES THE NUMBER OF PAGES OF
                                 PROCESS ALLOCATION REGION SPACE FOR PROSTRT TO CREATE.
```

PAR

Page

PAR

```
NAME=MPW_WRTCLUSTER,-
SIZE=WORD,-
TYPE=<SYSGEN,SYS>,-
                                         UNIT=Pages
```

MODIFIED PAGE LIST HIGH LIMIT - THRESHOLD AT WHICH TO BEGIN WRITING MODIFIED PAGES.

PARAMETER ADDRESS=MPW\$GW\_HILIM,-DEFAULT=500,-MIN=0,-MAX=16384,-NAME = MPW HILIMIT, -SIZE = WORD, -TYPE=<SYSGEN,SYS>,-

MODIFIED PAGE LIST LOW LIMIT - THRESHOLD AT WHICH MODIFIED PAGE WRITING WILL NORMALLY STOP. WRITING STARTED AT THE HIGH LIMIT AND PAGES ARE WRITTEN IN CHUNKS CONTROLLED BY THE CLUSTER FACTOR. WHEN THE LENGTH OF THE MODIFIED PAGE LIST HAS BEEN REDUCED BELOW THE LOW LIMIT, WRITING CEASES UNTIL ENOUGH PAGES HAVE BEEN ADDED TO EXCEED THE HIGH LIMIT.

PARAMETER ADDRESS=MPW\$GW\_LOLIM,-DEFAULT=32,-MIN=0,-MAX=16384,-NAME = MPW\_LOLIMIT, -SIZE=WORD .-TYPE=<SYSGEN,SYS>,-UNIT=Pages

UNIT=Pages

MODIFIED PAGE WRITER I/O PRIORITY. THIS PARAMETER SETS THE PRIORITY OF I/O TRANSFERS INITIATED BY THE MODIFIED PAGE WRITER.

ADDRESS=MPW\$GB\_PRIO,-PARAMETER DEFAULT=4,-MIN=0,-MAX=31,-NAME=MPW\_PRIO,-SIZE=BYTE,-TYPE=<SPECIAL, DYNAMIC>

SWAPPER I/O PRIORITY. THIS PARAMETER SETS THE PRIORITY OF I/O TRANSFERS INITIATED BY THE SWAPPER.

ADDRESS=SWP\$GB\_PRIO,-PARAMETER DEFAULT=4,-MIN=0 MAX=31 .-NAME = SWP\_PRIO, - ; SIZE = BYTE, -TYPE=<SPECIAL, DYNAMIC>

MODIFIED PAGE WRITER LOWER LIMIT THRESHOLD STOPPING USE OF MODIFIED PAGE WRITER FROM BEING USED AS PRIMARY MECHANISM TO RECOVER MEMORY.

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
```

```
16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
```

Page 27 (1)

```
Page fault rate high threshold. This parameter sets the upper page fault
              rate threshold for automatic working set adjustment.
                     PARAMETER
                                       ADDRESS=SCH$GL_PFRATH,- ;
                                       DEFAULT=120,-
                                       MIN=C -
                                       NAME = PFRATH . -
SIZE=LONG,-
                                       TYPE=<SYS, DYNAMIC, MAJOR>,-
                                      UNIT=Flts/10Sec ;
              Page fault rate system threshold. This parameter sets the target system page
              fault threshold.
                                       ADDRESS=SCH$GL_PFRATS,-;
                     PARAMETER
                                       DEFAULT=0,-
                                       MIN=0.- :
                                       NAME = PFRATS . -
                                       SIZE=LONG,-
                                       TYPE=<SPECIAL, DYNAMIC>,-
                                       UNIT=Flts/10Sec ;
              Working set increment. This parameter sets the number of pages to increase the
              working set size to compensate for a high page fault rate.
                                       ADDRESS=SCH$GL_WSINC,- ;
                     PARAMETER
                                       DEFAULT=150,-
                                      MIN=0.-
                                      NAME=WSINC .-
                                      SIZE=LONG,-
                                       TYPE=<SYS, DYNAMIC, MAJOR>,-
                                      UNIT=Pages
              Working set decrement. This parameter sets the number of pages to decrease
              the working set to compensate for a page fault rate below the lower threshold.
                                      ADDRESS=SCH$GL_WSDEC,- ;
DEFAULT=35,- ;
                     PARAMETER
                                      MIN=0,-
                                      NAME = WSDEC . -
                                      SIZE=LONG,-
       1396
1397
1398
1399
                                      TYPE=<SYS, DYNAMIC, MAJOR>,-
                                      UNIT=Pages
              Working set minimum. Sets the minimum working set size to ever be set
      1400
              by the automatic adjustment logic.
                                       ADDRESS=SCH$GW_AWSMIN,- ;
                     PARAMETER
                                      DEFAULT=50,-
                                      MIN=0,-
NAME=AWSMIN,-
      1406
1407
1408
1409
1410
                                      SIZE=WORD,-
                                       TYPE=<SYS, DYNAMIC>,-;
                                      UNIT=Pages
              Working set measurement interval. Sets the minimum interval of compute
            ; Working set measurement interval. Sets the r
; time for the measurement of page fault rate.
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
PARAMETER
V04-000
                                                                                                             VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                              Page
                                                                                   ADDRESS=SCH$GL_AWSTIME,-
DEFAULT=20,-;
                                                                PARAMETER
                                                                                   MIN=1.-
                                                                                   NAME = ÁWSTIME , -
                                          SIZE=LONG,-
                                                                                   TYPE=<SYS, DYNAMIC>,-;
                                                                                   UNIT=10Ms
                                                          Swap rate control. This parameter sets the swapping rate and serves to limit
                                                          the consumption of disk bandwidth by swapping.
                                                                                   ADDRESS=SCH$GL_SWPRATE,-
DEFAULT=500,-;
                                                                PARAMETER
                                                                                   MIN=0.-
                                                                                   NAME=SWPRATE .-
                                                                                   SIZE=LONG,-;
TYPE=<SPECIAL,DYNAMIC>,-
UNIT=10Ms/Swap;
                                                         Desired process page count for an outswap swap. This parameter sets the
                                                         number of pages to attempt to reduce a working set to before starting the
                                                         outswap.
                                                                PARAMETER
                                                                                   ADDRESS=SWP$GL_SWPPGCNT,-
                                                                                   DEFAULT=60,-
                                                                                   MIN=0,-
                                                                                   NAME = SWPOUTPGCNT, -
                                                                                   SIZE=LONG,-
                                                                                   TYPE=<SYS, DYNAMIC>,-
                                                                                   UNIT=Pages
                                                         Swap file allocation increment value. The size in blocks to use to backup
                                                         swap file space allocation in the swap or page file. Space in the file will
                                                 1446
1447
1448
                                                         be allocated multiples of this unit up to wsquota to guarantee swap space.
                                                                PARAMETER
                                                                                   ADDRESS=SWP$GW_SWPINC,-
                                                                                   DEFAULT=96,-
                                                                                   MIN=16,-
                                                                                   NAME = SWPALLOCINC, -
                                                                                   SIZE=WORD,-
TYPE=<SPECIAL>,-
                                                                                   UNIT=Blocks
```

PARAMETER

I/O time allowance. This parameter sets the number of 10 millisecond units to charge the current residence quantum for each voluntary wait.

ADDRESS=SCH\$GW\_IOTA,-DEFAULT=2,-

NAME=IOTA,-SIZE=WORD,-TYPE=<SPECIAL,DYNAMIC>,-

MIN=0,-MAX=32767,-

UNIT=10Ms

The correct value approximates the cost of a disk I/O neglecting wait time.

Page

```
PARAMETER
V04-000
```

```
VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                                                  29
SYSGEN PARAMETERS
                                Elapsed realtime to cause a HIB or LEF process to look like it is in longwait. This parameter sets the number of 1 second units
                                that need to have elapsed. Longwait processes are one of the most
                                eligible to attempt to recover pages from when a shortage is detected.
      ADDRESS=SCH$GW_LONGWAIT,-
DEFAULT=30,-;
                                PARAMETER
                                                     MIN=0,-;
MAX=65535,-
                                                     NAME=LONGWAIT,-
                                                     SIZE=WORD,-
                                                      TYPE=<SYS, DYNAMIC>,-
              UNIT=Seconds
                                Elapsed realtime to cause a low priority COM process to look like it is dormant. This parameter sets the number of 1 second units
                                that need to have elapsed. Dormant processes are one of the most
                                eligible to attempt to recover pages from when a shortage is detected.
                                                     ADDRESS=SCH$GW_DORMANTWAIT,-
DEFAULT=10,-;
                                PARAMETER
                                                     MIN=0,-;
MAX=65535,
                                                     NAME = DORMANTWAIT, -
SIZE = WORD, -
                                                     TYPE=<SYS, DYNAMIC>,-
                                                     UNIT=Seconds
                                Swap fail count. This parameter sets the number of consecutive swap schedule failures to occur before the swap schedule algorithm changes
                                to ignore the swap quantum protection.
              1500
1501
1502
1503
1504
1506
1506
1508
1510
1511
1513
                                                     ADDRESS=SCH$GW_SWPFAIL,-
DEFAULT=20,-;
                                PARAMETER
                                                     MIN=0,-;
MAX=32767,-
NAME=SWPFAIL,-
                                                     SIZE=WORD
                                                     TYPE=<SPECIAL, DYNAMIC> ;
                                These are reserved parameters for undefined use by either Digital
                                or user written system services.
                                This is the start of the Digital reserved parameters.
                                                     ADDRESS=SGN$GL_VMSD1,- ;
DEFAULT=0,- ;
                                PARAMETER
                                                     MIN=0,-
                                                     NAME = VMSD1 , -
                                                     SIZE=LONG,-
TYPE=<SPECIAL,DYNAMIC> ;
                                                     ADDRESS=SGN$GL_VMSD2.- ;
                                PARAMETER
                                                     DEFAULT=0,-
```

- PARAMETER DESCRIPTORS FOR SYSPARAM

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                                      30
                                                                                                                                             Page
                                                             MIN=0,-;
NAME=VMSD2,-;
SIZE=LONG,-;
TYPE=<SPECIAL,DYNAMIC>;
                 1526
1527
1528
1529
1530
1531
1532
                                                              ADDRESS=SGN$GL_VMSD3,-;
DEFAULT=0,-;
MIN=0,-;
                                     PARAMETER
                                                              NAME=VMSD3,-;
SIZE=LONG,-;
TYPE=<SPECIAL,DYNAMIC>;
                                                              ADDRESS=SGN$GL_VMSD4,- ;
DEFAULT=0,- ;
                                     PARAMETER
                                                              MIN=0.- :
                                                              NAME=VMSD4,-;
SIZE=LONG,-;
TYPE=<SPECIAL,DYNAMIC>;
                                                              ADDRESS=SGN$GL_VMS5,-
DEFAULT=0,-;
                                     PARAMETER
                                                              MIN=0.-
                                                              NAME = VMS5, -
                                                              SIZE=LONG.-
TYPE=<SPECIAL>
                 1550
                                                              ADDRESS=SGN$GL_VMS6,-
                                     PARAMETER
                                                              DEFAULT=0,-
                                                              MIN=0,- ;
                                                              NAME=VMS6.-
SIZE=LONG.-
TYPE=<SPECIAL>
        000C
        000C
000C
                                                              ADDRESS=SGN$GL_VMS7,-
DEFAULT=0,-;
                                     PARAMETER
        000C
                                                              MIN=0,-
                                                              NAME=VMS7.-
SIZE=LONG.-
TYPE=<SPECIAL>
        000C
        000C
                                                              ADDRESS=SGN$GL_VMS8,-
                                     PARAMETER
                                                              DEFAULT=0,-
                                                              MIN=0.-
                                                              NAME = VMS8 .-
SIZE = LONG .-
                                                              TYPE=<SPECIAL>
        000C
000C
000C
000C
000C
000C
                                     This is the start of the user reserved sysgen parameters.
                                                              ADDRESS=SGN$GL_USERD1,-;
DEFAULT=0,-;
                                     PARAMETER
                                                              MIN=0.-
                                                              NAME=USERD1,-
                                                              SIZE=LONG,-
                                                              TYPE=<DYNAMIC>
```

```
PARAMETER
V04-000
                                                                                                    16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                            - PARAMETER DESCRIPTORS FOR SYSPARAM
                                                                                                                                                                        Page
                                                                                                                                                                                (1)
                                            SYSGEN PARAMETERS
                                                                                                  ADDRESS=SGN$GL_USERD2,-;
DEFAULT=0,-;
                                                                             PARAMETER
                                                                                                   MIN=0.-
                                                                                                   NAME=USERD2 .-
                                                                                                   SIZE=LONG .-
                                                                                                   TYPE=<DYNAMIC>
                                                                                                  ADDRESS=SGN$GL_USER3,- ;
DEFAULT=0,- ;
                                                                             PARAMETER
                                                                                                   MIN=0,-
                                                                                                   NAME=USER3,-
                                                                                                   SIZE=LONG,-
                                                                                                   TYPE=<>
                                                                                                  ADDRESS=SGN$GL_USER4,- ;
DEFAULT=0,- ;
                                                                             PARAMETER
                                                                                                   MIN=0.-
                                                                                                  NAME=USER4,-
SIZE=LONG,-
                                                           1601
1602
1603
                                                                                                   TYPE=<>
                                                           1604
                                                                             Extra CPU time. This parameter sets the number of 10 millisecond
                                                           1606
1607
1608
1609
                                                                             units to be allowed as an extension when CPU time expires. One
                                                                             extension is allowed for each access mode.
                                                                                                  ADDRESS=SGN$GL_EXTRACPU,-
DEFAULT=1000,- ; 10 Seconds
                                                                             PARAMETER
                                                           1610
1611
1612
1613
1614
1615
                                                                                                   MIN=0,-
                                                                                                  NAME = EXTRACPU, -
                                                                                                   SIZE=LONG,-
                                                                                                   TYPE=<SYS, DYNAMIC>,-
                                                                                                  UNIT=10Ms
                                                           1616
1617
                                                           1618
                                                                    Maximum group code for system UIC
                                                   ÖÖÖC
                                                                             PARAMETER
                                                                                                   ADDRESS=EXE$GL_SYSUIC,- ;
                                                                                                   DEFAULT=8,-
                                                                                                  MIN=1,-
MAX=32768,-
                                                                                                   NAME = MAXSYSGROUP . -
                                                                                                  SIZE=LONG,-
TYPE=<SYS,DYNAMIC>,-
UNIT=<UIC Group>
                                                   000C
000C
000C
000C
000C
000C
000C
                                                                    Maximum time for a device to languish in mount verification before giving up.
                                                                                                  ADDRESS=IOC$GW_MVTIMEOUT,-
DEFAULT=600,-
MIN=1,-
MAX=64000,-
                                                                             PARAMETER
                                                                                                                                               : 10 minute default
                                                                                                  NAME=MVTIMEOUT, -
SIZE=WORD, -
TYPE=<SYS, DYNAMIC>, -
```

UNIT=Seconds

```
0000
       1662
                Default maximum message size for Mailbox creation
0000
000C
000C
000C
000C
                                          ADDRESS=IOC$GW_MBXMXMSG,-
DEFAULT=256,-;
       1664
                       PARAMETER
       1665
                                          MIN=64,-
MAX=64000,-
       1666
       1667
       1668
                                           NAME = DEFMBXMXMSG . -
       1669
SIZE=WORD,-
                                           TYPE=<SYS, DYNAMIC>,-
                                           UNIT=Bytes
       1672
               Default number of messages for Mailbox creation
       1674
                       PARAMETER
                                           ADDRESS=IOC$GW_MBXNMMSG,-
       1676
                                           DEFAULT=16,-
                                           MIN=1 .-
                                           NAME = DEFMBXNUMMSG . -
                                          SIZE=WORD,-
TYPE=<SYS,DYNAMIC>,-
       1680
       1681
                                           UNIT=Messages
       1682
1683
                       DESIRED FREE LIST LENGTH - SPECIFIES THE NUMBER OF FREE PAGES TO
                                          BE MAINTAINED AVAILABLE BY THE SWAPPER.
000C
000C
000C
000C
000C
000C
000C
                       PARAMETER
                                          ADDRESS=SGN$GL_FREELIM,-
DEFAULT=32,-
                                           MIN=16.-
                                           NAME = FREELIM, -
                                           SIZE=LONG,-
                                           TYPE=<SYS, SYSGEN, MAJOR>,-
       1691
       1692
                                           UNIT=Pages
```

Target free list length - specifies the number of free pages that the swapper will attempt to make available

when correcting for free list < FREELIM.

1694 1695

1696

```
16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                            VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
SYSGEN PARAMETERS
     ADDRESS=SGN$GL_FREEGOAL,-
DEFAULT=200,-
MIN=16,-
             1698
                             PARAMETER
             1699
1700
             1701
                                                NAME = FREEGOAL .-
             1702
                                                SIZE=LONG,-
                                                 TYPE=<SYS, MAJOR>,-
             1704
                                                UNIT=Pages
             1706
1707
1708
1709
                             DESIRED FREE LIST LENGTH THAT MUST EXIST TO ALLOW PROCESSES
                                                TO GROW PAST WSQUOTA.
                                                ADDRESS=SCH$GL_GROWLIM,-;
                             PARAMETER
             1710
                                                DEFAULT=63,-
             1711
                                                MIN=0,-
             1712
                                                NAME = GROWL IM . -
                                                SIZE=LONG,-
             1714
                                                 TYPE=<SYS, DYNAMIC, MAJOR>,-
             1715
                                                UNIT=Pages
             1716
1717
1718
1719
      000C
000C
000C
                             DESIRED FREE LIST LENGTH THAT MUST EXIST TO ALLOW PROCESSES
                                                TO GROW PAST WSQUOTA.
                             PARAMETER
                                                ADDRESS=SCH$GL_BORROWLIM,-
      0000
                                                DEFAULT=300,-
      ŎŎŎĊ
                                                MIN=0.-
     000C
                                                NAME = BORROWLIM, -
                                                SIZE=LONG,-
      000C
                                                TYPE=<SYS, DYNAMIC, MAJOR>,-
      000C
                                                UNIT=Pages
      000C
      000C
                     NUMBER OF RETRIES TO PERFORM WHEN TRYING TO LOCK A MULTI-PROCESSOR
      0000
                     DATA STRUCTURE
     000C
             1730
             1731
                                                ADDRESS=EXESGL_LOCKRTRY,-
                             PARAMETER
     000C
000C
000C
000C
             1732
1733
                                                DEFAULT=100000,-
                                                MIN=1 .-
             1734
                                                NAME=LOCKRETRY,-
             1735
                                                SIZE=LONG,-
             1736
1737
                                                TYPE=<SPECIAL, DYNAMIC>,-;
      0000
                                                UNIT=Retries
      000C
             1738
     000C
000C
000C
             1739
                     Maximum DR32 data rate
                                                ADDRESS=IOC$GW_XFMXRATE,-
DEFAULT=236,- ;
                             PARAMETER
      0000
      0000
                                                MIN=0.-
      ŎŎŎĊ
                                                MAX=255,-
      OOOC
                                                NAME = XFMAXRATE, -
      ÖÖÖC
                                                SIZE=WORD,-
      ŎŎŎČ
                                                TYPE=<SYS, DYNAMIC>,-
      0000
             1748
                                                UNIT=Special
      ÖÖÖÖ
             1750
1751
1752
1753
      ÖÖÖC
                     Number of Unibus map registers to preallocate for LPA11
      000C
                             PARAMETER
                                                ADDRESS=IOC$GW_LAMAPREG,-
                                                DEFAULT=0,-
```

PAR

V04

33

Page

- PARAMETER DESCRIPTORS FOR SYSPARAM

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                        16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                                      VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                                            Page
SYSGEN PARAMETERS
                                                      MIN=0,-
MAX=255,-
NAME=LAMAPREGS,-
SIZE=WORD,-
      1754
1755
1756
1757
1758
1763
1763
1764
1768
1768
1769
                                                       TYPE=<SYS, SYSGEN>,-
                                                       UNIT=Mapregs
                        Number of SPT entries to preallocate for use by real time processes
                        connecting to devices via the connect to interrupt driver.
                                PARAMETER
                                                       ADDRESS=EXESGL_RTIMESPT,-
                                                       DEFAULT=0,-
                                                       MIN=0.-
                                                       NAME = REALTIME_SPTS, -
                                                       SIZE=LONG,-
               1771
                                                       TYPE=<SYS, SYSGEN>,-
               1772
                                                       UNIT=Pages
              1774
1775
1776
1777
                        Number of pages created for command interpreter symbol table.
               1778
1779
                                                       ADDRESS=EXE$GL_CLITABL,-
                                PARAMETER
                                                       DEFAULT=60,-
MIN=10,-
              1780
1781
1782
1783
1784
1786
1786
1788
1798
1793
1796
1797
1798
1799
                                                       MAX=128 .-
                                                       NAME=CLISYMTBL .-
                                                       SIZE=LONG,-
                                                       TYPE=<SYS, SYSGEN, DYNAMIC>,-
                                                      UNIT=Pages
                        Initial size of lock id table (and growing increment).
                                                      ADDRESS=LCK$GL_IDTBLSIZ,-
DEFAULT=200,-
MIN=40,-
                                PARAMETER
                                                       MAX=65535.
                                                       NAME = LOCKIDTBL , -
                                                       SIZE=LONG,-
                                                       TYPE=<SYS, SYSGEN, MAJOR>,-
                                                       UNIT=Entries
               1800
               1801
                        Maximum size of lock id table.
              1802
1803
                                                      ADDRESS=LCK$GL_IDTBLMAX,-
DEFAULT=800,-
MIN=200,-
MAX=65535,-
                                 PARAMETER
               1805
               1806
1807
1808
1809
1810
                                                       NAME = LOCKIDTBL_MAX, -
                                                       SIZE=LONG,-
                                                       TYPE=<SYS, SYSGEN, MAJOR, DYNAMIC>,-
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                             VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                                Page
                                                 UNIT=Entries
      Size of resource hash table.
                                                 ADDRESS=LCK$GL_HTBLSIZ,-
                              PARAMETER
                                                 DEFAULT=64 .-
                                                 MIN=1,-
                                                 MAX=8192.-
                                                 NAME = RESHASHTBL , -
                                                 SIZE=LONG,-
TYPE=<SYS,SYSGEN,MAJOR>,-
UNIT=Entries
                      Deadlock detection timeout period
                             PARAMETER
                                                 ADDRESS=LCK$GL_WAITTIME,-
                                                 DEFAULT=10,-
             MIN=0,-
                                                 NAME = DEADLOCK_WAIT, -
                                                 SIZE=LONG,-
                                                 TYPE=<SYS, DYNAMIC>,-
                                                 UNIT=Seconds
                      SCS allocation counts - Buffer Descriptor Table entries
                             PARAMETER
                                                 ADDRESS=SCS$GW_BDTCNT,-
                                                 DEFAULT=50,-
                                                 MIN=0,-
MAX=32767,-
                                                 NAME = SCSBUFFCNT, -
                                                 SIZE=WORD,-
TYPE=<SYSGEN,SCS>,-
                                                 UNIT=Entries
                      SCS allocation counts - Connect Descriptor Table entries
                                                ADDRESS=SCS$GW_CDTCNT,-
DEFAULT=40,-
MIN=2,-
MAX=32767,-
NAME=SCSCONNCNT,-
                             PARAMETER
                                                 SIZE=WORD .-
                                                 TYPE=<SYSGEN,SCS>,-
                                                 UNIT=Entries
                      SCS allocation counts - Response Descriptor Table entries
                                                 ADDRESS=SCS$GW_RDTCNT,-
DEFAULT=100,-
                             PARAMETER
                                                 MIN=0,-
```

V04

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                               MAX=32767,-
NAME=SCSRESPCNT,-
SIZE=WORD,-
TYPE=<SYSGEN,SCS>,-
        UNIT=Entries
                 SCS maximum datagram size
                                                              ADDRESS=SCS$GW_MAXDG,-
DEFAULT=576,-
MIN=28,-
MAX=985,-
NAME=SCSMAXDG,-
SIZE=WORD,-
TYPE=<SYSGEN,SCS>,-
                                      PARAMETER
                                                               UNIT=Bytes
                            SCS maximum sequenced message size
                                                               ADDRESS=SCS$GW_MAXMSG,-
DEFAULT=112,-
MIN=52,-
MAX=985,-
NAME=SCSMAXMSG,-
                                      PARAMETER
                                                               SIZE=WORD .-
                                                               TYPE=<SYSGEN,SCS>,-
                                                               UNIT=Bytes
                 1900
1901
1902
1903
1904
1905
1906
1907
1908
1909
1910
1911
1912
                            SCS flow control cushion
                                                               ADDRESS=SCS$GW_FLOWCUSH,-
                                      PARAMETER
                                                               DEFAULT=1,-
                                                               MIN=0,-
MAX=16,-
                                                               NAME = SCSFLOWCUSH, -
                                                               SIZE=WORD,-
TYPE=<SCS,DYNAMIC>,-
UNIT=Credits
                  1913
                 1914
1915
                            SCS system id (unique 48 bit number per system)
                 1916
                                                               ADDRESS=SCS$GB_SYSTEMID,-
                                      PARAMETER
                 1918
                                                               DEFAULT=0,-
                                                               NAME = SCSSYSTEMID, -
                 1920
1921
1922
1923
1923
                                                               SIZE=LONG,-
                                                               TYPE=<SYSGEN,SCS>,-
                                                               UNIT=Pure-number
                                      PARAMETER
                                                               ADDRESS=SCS$GB_SYSTEMIDH,-
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                       16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                          Page
                                                                                                                                  37
                                                      DEFAULT=0,-
NAME=SCSSYSTEMIDH,-
       SIZE=LONG .-
                                                      TYPE=<SYSGEN,SCS>,-
                                                      UNIT=Pure-number
               1933
1933
1934
1935
1937
1938
1938
1940
1941
1943
                        SCS system node name
                                                      ADDRESS=SCS$GB_NODENAME,-
                                PARAMETER
                                                      DEFAULT=<^A/
                                                                          /> -
                                                      MIN=<^A/
                                                      MAX=<^A/ZZZZ/>,-
                                                      NAME = SCSNODE , -
                                                      SIZE=QUAD,-
TYPE=<ASCII,SYSGEN,SCS>,-
                                                      UNIT=Ascii
               1944
                        SCA process poller - polling interval
               1946
1947
1948
1951
1955
1955
1955
1955
1966
1967
1977
1975
1975
                                                      ADDRESS=SCS$GW_PRCPOLINT,-
DEFAULT=15,-
                                PARAMETER
                                                      MIN=1,-
MAX=32767,-
                                                      NAME=PRCPOLINTERVAL,-
                                                      SIZE=WORD,-
                                                      TYPE=<SCS, DYNAMIC>,-
                                                      UNIT=Seconds
                        CI port - timeout for START/STACK sequence, also basic driver wakeup interval
                                PARAMETER
                                                      ADDRESS=SCS$GW_PASTMOUT,-
                                                      DEFAULT=5,-
                                                      MIN=1,-
                                                      MAX=99 .-
                                                      NAME = PASTIMOUT, -
                                                      SIZE=WORD,-
                                                      TYPE=<SCS, DYNAMIC>,-
                                                      UNIT=Seconds
                        CI port - number of DG buffers to queue for START handshake
                                                      ADDRESS=SCS$GW_PAPPDDG,-
                                PARAMETER
                                                      DEFAULT=4,-
               1976
1977
1978
1979
1980
1981
                                                      MIN=1,-
MAX=16,-
                                                      NAME = PASTDGBUF . -
                                                      SIZE=WORD,-
TYPE=<SCS>,-
                                                      UNIT=Buffers
```

Page

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                           VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR;1
      CI port - number of ports to poll each interval (for future expansion)
                            PARAMETER
                                                ADDRESS=SCS$GB_PANPOLL,-
                                                DEFAULT=16 .-
             1989
1990
1991
1993
1993
1994
                                                MIN=1,-
                                                MAX=223 .-
                                                NAME = PANUMPOLL , -
                                                SIZE=BYTE,-
TYPE=<SCS,DYNAMIC>,-
                                                UNIT=Ports
             1996
1997
1998
                     CI port - maximum port # to poll each interval (for future expansion)
             1999
2000
2001
2002
2003
                             PARAMETER
                                                ADDRESS=SCS$GB_PAMXPORT,-
                                                DEFAULT=15,-
                                                MIN=0,-
                                                MAX=223 .-
                                                NAME=PAMAXPORT,-
                                                SIZE=BYTE,-
                                                TYPE=<SCS, DYNAMIC>,-
                                                UNIT=Port-number
                     CI port - time between poll initiates
                             PARAMETER
                                                ADDRESS=SCS$GW_PAPOLINT,-
                                                DEFAULT=5,-
                                                MIN=1,-
                                                MAX=32767 .-
                                                NAME = PAPOLLINTERVAL , -
                                                SIZE=WORD,-
                                                TYPE=<SCS, DYNAMIC>,-
                                                UNIT=Seconds
                     CI port - time between check for SYSAP's waiting for pool
                                                ADDRESS=SCS$GW_PAPOOLIN,-
DEFAULT=15,-
                             PARAMETER
                                                MIN=1,-
MAX=32767,-
                                                NAME = PAPOOL INTERVAL . -
                                                SIZE=WORD .-
                                                TYPE=<SCS, DYNAMIC>,-
                                                UNIT=Seconds
                     CI port - Flags including sanity timer enable/disable
```

ADDRESS=SCS\$GB\_PASANITY,-

PARAMETER

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                   16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                  DEFAULT=1,-
MIN=0,-
      MAX=1 .-
                                                  NAME = PASANITY , -
                                                  SIZE=BYTE,-
TYPE=<SCS,DYNAMIC>,-
                                                  UNIT=Boolean
                      CI port - Flags including CI remote port polling enable/disable
                              PARAMETER
                                                  ADDRESS=SCS$GB_PANOPOLL,-
                                                  DEFAULT=0,-
                                                  MIN=0,-
                                                  MAX=1.-
                                                  NAME = PANOPOLL , -
                                                  SIZE=BYTE,-
                                                  TYPE=<SCS, DYNAMIC>,-
                                                  UNIT=Boolean
                       This is the start of the PEDRIVER reserved SYSGEN parameters.
                              PARAMETER
                                                  ADDRESS=SGN$GL_PE1,-
                                                  DEFAULT=0 .-
                                                  MIN=0,-
                                                  NAME = PE1, -
SIZE = LONG, -
                                                  TYPE=<SPECIAL, DYNAMIC>
                              PARAMETER
                                                  ADDRESS=SGN$GL_PE2,-
                                                  DEFAULT=0,-
                                                  MIN=0,-
                                                  NAME=PE2.-
SIZE=LONG.-
TYPE=<SPECIAL,DYNAMIC>
                                                  ADDRESS=SGN$GL_PE3,-
                              PARAMETER
                                                  DEFAULT=0,-
                                                  MIN=0,-
                                                  NAME = PE3, -
SIZE = LONG, -
                                                  TYPE=<SPECIAL, DYNAMIC>
                              PARAMETER
                                                  ADDRESS=SGN$GL_PE4,-
                                                  DEFAULT=0,-
                                                  MIN=0,-
                                                  NAME=PE4,-
SIZE=LONG,-
TYPE=<SPECIAL,DYNAMIC>
                              PARAMETER
                                                  ADDRESS=SGN$GL_PE5,-
                                                  DEFAULT=0,-
                                                  MIN=0 .-
                                                  NAME=PE5,-
```

PAI

```
16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
SYSGEN PARAMETERS
                           Size of PROCESS space logical name hash table.
                                                              ADDRESS=LNM$GL_HTBLSIZP,-
DEFAULT=128,-
                                     PARAMETER
       MIN=1 .-
                                                              MAX=16383,-
                                                              NAME=LNMPHASHTBL,-
                                                              SIZE=LONG,-
TYPE=<SYS,SYSGEN>,-
                                                              UNIT=Entries
                 21667
21667
21667
21689
2177
2177
2177
2177
2178
2183
2183
                                     . IF
                                                 NOT_DEFINED GETSYISW
                                     PERMANENT DEFAULT SYSTEM FLAGS
                                     .ALIGN LONG
                                                 NDF , PRMSW
                         EXESGL_DEFFLAGS::
                                     .ENDC
                                                 <1aexe$v syspaging>-
!<1aexe$v poolpging>-
!<1aexe$v sbierr>-
!<1aexe$v sbierr>-
!<1aexe$v bugreboot>-
!<1aexe$v crdenabl>-
!<1aexe$v bugdump>-
!<1aexe$v concealed>-
!<1aexe$v jobqueues>-
!<1aexe$v shrf11acp>
                                                                                          ENABLE SYSTEM CODE PAGING ENABLE SYSTEM POOL PAGING
                                     .LONG
                                                                                          SBI ERROR DETECTION
AUTOMATIC REBOOT ON BUGCHECK
                                                                                          ENABLE CRD ERROR DETECTION
SYSTEM DUMP ON BUGCHECK
                                                                                         ENABLE USE OF CONCEALED DEVICES 
Enable job controller queues 
SHARE F11ACP
                                     .ENDC
                                                 ; NOT_DEFINED GETSYISW
                 BUGCHECK REBOOT - ENABLES AUTOMATIC REBOOT ON BUGCHECK
                                     .LIST ME
.NLIST CND
                                     PARAMETER
                                                              ADDRESS=EXE$GL_DEFFLAGS,-
                                                              DEFAULT=1,-
                                                              MAX=1,-
                                                              MIN=0 .-
                                                              NAME = BUGREBOOT .
                                                              BIT=EXESV_BUGREBOOT, -
                                                              TYPE= <DYNAMIC, SYS>,-
                                                              UNIT=Boolean
                                     .NLIST ME
                                                 CND
                                     .LIST
                                     CRD ERROR ENABLE - ENABLES DETECTION AND LOGGING OF MEMORY CRD ERRORS
                                                              ADDRESS=EXESGL_DEFFLAGS,-
DEFAULT=1,-
                                     PARAMETER
        000c
000c
                                                              MAX=1,-
                                                              MIN=0,-
                                                              NAME = CRDENABLE,
                                                              BIT=EXESV_CRDENABL,-:
TYPE=<SYS,SYSGEN>,-:
```

- PARAMETER DESCRIPTORS FOR SYSPARAM

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                     16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                             42
                                                                                                                     Page
                                                   UNIT=Boolean
                               BUGCHECK DUMP ENABLE - ENABLE SYSTEM DUMP ON BUGCHECK
                                                   ADDRESS=EXE$GL_DEFFLAGS,-
DEFAULT=1,-;
                               PARAMETER
                                                    MAX=1,-
                                                   MIN=0.-
                                                    NAME = DUMPBUG . -
                                                   BIT=EXE$V_BUGDUMP,-
TYPE=<SYS>,-
                                                   UNIT=Boolean
                               FATAL BUGCHECK - TURNS ALL CONTINUABLE BUGCHECKS INTO FATAL BUGCHECKS
                               PARAMETER
                                                   ADDRESS=EXESGL_DEFFLAGS,-
DEFAULT=0,-;
                                                    MAX=1,-
                                                    MIN=0,-
                                                   NAME = BUGCHECKFATAL ,-;
BIT = EXE$V FATAL BUG, -
TYPE = < SYS, DYNAMIC > ,-;
                                                   UNIT=Boolean
                               MULTIPLE ACP - SPECIFIES THAT SEPARATE ACPS ARE TO BE CREATED FOR
                                                  EACH CLASS OF DISK.
                               PARAMETER
                                                    ADDRESS=EXE$GL_DEFFLAGS,-;
                                                    DEFAULT=0,-
                                                    MAX=1,-
                                                   MIN=0,-
                                                   NAME=ACP MULTIPLE,-
BIT=EXESV MULTACP,-
TYPE=<ACP,DYNAMIC>,-
                                                   UNIT=Boolean
                               AUTO CONFIGURATION INHIBIT - INHIBITS THE AUTOMATIC CONFIGURATION
                                         OF DEVICES.
                                                   ADDRESS=EXE$GL_DEFFLAGS,-;
DEFAULT=0,-;
                               PARAMETER
                                                    MAX=1,-
                                                   MIN=0,-
                                                   NAME=NOAUTOCONFIG,-
BIT=EXE$V_NOAUTOCNF,-
TYPE=<SPECIAL,DYNAMIC>,-;
                                                   UNIT=Boolean
                               NO CLOCK - INHIBITS THE STARTING OF THE INTERVAL TIMER FOR DEBUGGING
                                         PURPOSES.
                                                   ADDRESS=EXE$GL_DEFFLAGS,-
DEFAULT=0,-;
                               PARAMETER
                                                    MAX=1,-
                                                   MIN=0.-
                                                   NAME = NOCLOCK , -
                                                   BIT=EXESV_NOCLOCK,-
```

(1)

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                                            VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR;1
SYSGEN PARAMETERS
                                                TYPE=<SPECIAL>,-
                                                UNIT=Boolean
                             CLUSTERING INHIBIT - INHIBITS ALL PAGE READ CLUSTERING
                                                ADDRESS=EXE$GL_DEFFLAGS,-
                             PARAMETER
                                                DEFAULT=0,-
                                                MAX=1,-
                                                MIN=0 .-
                                                NAME=NOCLUSTER,-
                                                BIT=EXE$V_NOCLUSTER,-
TYPE=<SPECIAL>,-
                                                UNIT=Boolean
                             ENABLE PAGING OF PAGED DYNAMIC POOL
                             PARAMETER
                                                ADDRESS=EXE$GL_DEFFLAGS,-
                                                DEFAULT=1,-
                                                MAX=1,-
                                                MIN=0.-
                                                NAME = POOL PAGING, -
                                                BIT=EXESV_POOLPGING,-
TYPE=<SPECIAL>,-;
                                                UNIT=Boolean
                             SBI ERROR DETECTION ENABLE
                                                ADDRESS=EXE$GL_DEFFLAGS,-
                             PARAMETER
                                                DEFAULT=1,-
                                                MAX=1,-
                                                MIN=0
                                                NAME=SBIERRENABLE,-
                                                BIT=EXE$V_SBIERR,-
TYPE=<SPECIAL>,-
                                                UNIT=Boolean
                             FORCE ENTRY OF TIME AT SYSTEM BOOT
                             PARAMETER
                                                ADDRESS=EXE$GL_DEFFLAGS,-
                                                DEFAULT=0,-
                                                MAX=1,-
                                                MIN=0
                                                NAME=SETTIME,-
BIT=EXE$V_SETTIME,-
TYPE=<SYS,SYSGEN>,-;
                                                UNIT=Boolean
                             ENABLE SHARING OF F11ACP
                                                ADDRESS=EXE$GL_DEFFLAGS,-
                             PARAMETER
                                                DEFAULT=1,-
                                                MAX=1,-
                                                MIN=0
                                                NAME=ACP SHARE -:
BIT=EXE$V SHRF11ACP,-
TYPE=<ACPS,-;
                                                UNIT=Boolean
```

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                  16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                       (1)
                                                                                                                Page
                             ENABLE PAGING OF SYSTEM CODE
                                                 ADDRESS=EXE$GL_DEFFLAGS,-;
DEFAULT=1,-;
                             PARAMETER
                                                 MAX=1,-
                                                 MIN=0.-
                                                 NAME=SYSPAGING,-
                                                 BIT=EXE$V_SYSPAGING,-
TYPE=<SPECIAL>,-
                                                 UNIT=Boolean
                             SELECT ALTERNATE AUTHORIZATION FILE - CAUSES SYSINIT TO MAKE A LOGICAL
                                       NAME REDIRECTING SYSUAF TO SYSUAFALT.
                                                 ADDRESS=EXE$GL_DEFFLAGS,-
DEFAULT=0,-;
                             PARAMETER
                                                 MAX=1,-
                                                 MIN=0 .-
                                                 NAME=UAFALTERNATE,-
                                                 BIT=EXE$V_SYSUAFALT,-
TYPE=<SYS,SYSGEN>,-
                                                 UNIT=Boolean
                             LEAVE SYSTEM WRITABLE - FOR DEBUGGING PURPOSES LEAVES SYSTEM CODE
                                       WRITABLE.
                             PARAMETER
                                                 ADDRESS=EXE$GL_DEFFLAGS,-
                                                 DEFAULT=0,-
                                                 MAX=1,-
                                                 MIN=0 .-
                                                 NAME = WRITABLESYS , - ;
                                                 BIT=EXESV SYSWRTABL, -;
TYPE=<SPECIAL>,-
                                                 UNIT=Boolean
                             Enable resource allocation checking
                             PARAMETER
                                                 ADDRESS=EXE$GL_DEFFLAGS,-
                                                 DEFAULT=0,-
                                                 MAX=1,-
                                                 MIN=0.-
                                                 NAME = RESALLOC .-
                                                 BIT=EXESV_RESALLOC,-
TYPE=<SPECIAL>,-
                                                 UNIT=Boolean
                             SET TO INHIBIT SYSTEM SERVICES ON A PER PROCESS BASIS
                                                 ADDRESS=EXESGL_DEFFLAGS,-
DEFAULT=0,-;
      000C
                             PARAMETER
      0000
                                                 MAX=1,-
      0000
                                                 MIN=0,-
                                                 NAME=SSINHIBIT .-
      000C
                                                 BIT=EXESV_SSINHIBIT, -:
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                                                                    (1)
                                                 16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                            VAX/VMS Macro V04-00
                                                                                                             Page
                                                                            [SYS.SRC]SYSPARAM.MAR: 1
                                                TYPE=<SPECIAL>,-
      UNIT=Boolean
                             RESET TO DISABLE THE USE OF CONCEALED DEVICES
                                                ADDRESS=EXESGL_DEFFLAGS,-
                             PARAMETER
                                                DEFAULT=1,-
                                                MAX=1,-
                                                MIN=0
                                                NAME=CONCEAL DEVICES,-;
BIT=EXESV_CONCEALED,-;
TYPE=<SPECIAL>,-
UNIT=Boolean
                             SAVEDUMP - IF THE DUMP IS IN THE PAGE FILE, SAVE IT UNTIL IT IS ANALYZED AND COPIED.
                             PARAMETER
                                                ADDRESS=EXESGL_DEFFLAGS,-
                                                DEFAULT=0,-
                                                MAX=1,-
                                                MIN=0 .-
                                                NAME = SAVEDUMP . -
                                                BIT=EXESV SAVEDUMP ,-
                                                UNIT=Boolean
                             CJFLOAD - Force CJF to be loaded as part of VMS during STARTUP
                    **JNL** this parameter is temporarily special and off
                             PARAMETER
                                                ADDRESS=EXESGL_DEFFLAGS,-
                                                DEFAULT=1,-
                   : *JNL **
                                                DEFAULT=0,-
                                                MAX=1,-
                                                MIN=0.-
                                                NAME = CJFLOAD , -:
                                                BIT=EXESV CJFLOAD,-
TYPE=<SYS5,-
                   : **JNL **
                                                TYPE=<SYS>,-
TYPE=<SPECIAL>,-
                                                UNIT=Boolean
                             CJFSYSRUJ - Force creation of Recovery Unit journal for system disk
                                                during STARTUP. Recovery will take place during creation of this journal.
                     **JNL** this parameter is temporarily special
                             PARAMETER
                                                ADDRESS=EXESGL_DEFFLAGS,-
                                                DEFAULT=0,-
                                                MAX=1,-
                                                MIN=0 .-
                                                NAME = CJFSYSRUJ, -
                                                BIT=EXESV CJFSYSRUJ,-
TYPE=<SYS5,- ;
                    **JNL **
                                                TYPE= < SPECIAL>,-
                                                UNIT=Boolean
                             . IF
                                      NOT_DEFINED GETSYISW
```

PAR

V04

B 15

PAF

```
DYNAMIC SYSTEM CONTROL FLAGS.
                                          LONG
                              . ALIGN
                 EXESGL_DYNAMIC_FLAGS::
                                                                                    Dynamic SYSGEN flags
                                          ; NDF PRMSW
<1@EXESV_WRITESYSPARAMS>!-
<1@EXESV_BRK_TERM>;
; NOT_DEFINED GETSYISW
                              .ENDC
                              . LONG
                              .ENDC
                                          EXE, 0, <-
CLASS_PROT, -
WRITESYSPARAMS, -
                                                                                 : DEFINITION FOR EXESGL_DYNAMIC_FLAGS
: Do non-discretionary classification check
                              $VIELD
                                                                                    Write the active parameters to the system
                                          BRK_TERM,-
BRK_DISUSER,-
                                                                                    Associate on terminal in breakin detection
                                                                                    Disable user account on breakin
                              >
                                                       Perform the non-discretionary classification checks. This also is looked at by the XQP to determine of a classification block should be
                              CLASS_PROT -
                                                       added to the header of any created files.
                                                       ADDRESS=EXE$GL_DYNAMIC_FLAGS,- ;
DEFAULT=0,- ;
                              PARAMETER
                                                        MAX=1,-
                                                       MIN=0 .-
                                                       NAME=CLASS_PROT,-;
BIT=EXE$V_CLASS_PROT,-
TYPE=<DYNAMIC,SYS>,-
UNIT=Boolean
                             WRITESYSPARAMS - Set by SYSBOOT if a USE DEFAULT, USE "file", or a SET command is executed. Cleared if a USE CURRENT or WRITE CURRENT command is executed. If set STARTUP.COM will issue a WRITE CURRENT SYSGEN command.
                              PARAMETER
                                                        ADDRESS=EXESGL_DYNAMIC_FLAGS,- ;
                                                       DEFAULT=1 .-
                                                        MAX=1,-
                                                       MIN=0.-
                                                       NAME=WRITESYSPARAMS, -:
                                                       BIT=EXESV WRITESYSPARAMS, -;
TYPE=<DYNAMIC, SPECIAL>, -;
                                                       UNIT=Boolean
         2487
2488
2489
2490
2492
2493
2494
                              LGI_BRK_TERM -
                                                       Use the terminal name in the association string
                                                       used in LOGIN's breakin detection. If not set, breakin detection associates on username alone
                                                        for terminal logins.
                              PARAMETER
                                                       ADDRESS=EXESGL_DYNAMIC_FLAGS.- ;
                                                       DEFAULT=1,-
```

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                          16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                          47
                                                         MAX=1,-
                                                        MIN=0,-
NAME=LGI BRK TERM,-;
BIT=EXE$V BRK TERM,-;
TYPE=<DYNAMIC,LGI>,-;
UNIT=Boolean
       LGI_BRK_DISUSER - If enabled, set the DISUSER flag in the user's UAF record if a breakin attempt is detected.
                                                         This assures a permanent lockout of the user until re-enabled by the system manager.
                                  PARAMETER
                                                         ADDRESS=EXESGL_DYNAMIC_FLAGS,- ;
                                                         DEFAULT=0,-
                                                         MAX=1 .-
                                                         MIN=0.-
                                                         NAME = LGI BRK DISUSER, -;
BIT = EXE $ V BRK DISUSER, -;
TYPE = < DYNAMIC, LGI>, -;
                                                         UNIT=Boolean
                                  . IF
                                             NOT_DEFINED GETSYISW
                         STATIC SYSTEM CONTROL FLAGS.
       000C
000C
000C
                                  .ALIGN
                                             LONG
                                             NDF , PRMSW
                      EXESGL_STATIC_FLAGS::
                                                                                ; Static SYSGEN flags
       000C
                                             : NDF , PRMSW
                                             <1aEXESV_XQP_RESIDENT>!<1aEXESV_REBLDSYSD>
; NOT_DEFINED GETSYISW
                                  .LONG
                                  .ENDC
                                             EXE,O,<-
XQP RESIDENT,-
REBEDSYSD,-
                                  $VIELD
                                                                                  DEFINITION FOR EXESGL_STATIC_FLAGS
                                                                                  MEMORY RESIDENT XQP
                                                                                : REBUILD SYSTEM DISK IN SYSMOUNT
                                  . PAGE
                                  .SBTTL SYSTEM MESSAGE PARAMETERS
                         DEFINE THE CONTROL BITS IN EXESGL_MSGFLAGS
                                  $GBLINI GLOBAL
$VIELD EXE.O.<-
                                                                               : ENABLE MOUNT NOTIFICATION : ENABLE DISMOUNT NOTIFICATION
                                             MOUNTMSG .-
                                             DISMOUMSG .-
                                  >
                                  . IF
                                             NOT_DEFINED GETSYISW
                         DEFINE THE EXESGL_MSGFLAGS LONGWORD AND ITS INITIAL VALUE.
                                  .ALIGN
                                             LONG
                                             NDF , PRMSW
```

```
PARAMETER
V04-000
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                       VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                               48
                  EXESGL_MSGFLAGS::
                            .ENDC
                            .LONG
                            .ENDC
                                     : NOT_DEFINED GETSYISW
                           MOUNTMSG - CONTROLS OPERATOR NOTIFICATION OF VOLUME MOUNTING
                                              ADDRESS=EXESGL_MSGFLAGS,-
DEFAULT=0,-
                            PARAMETER
                                              MAX=1,-
                                              MIN=0 .-
                                              NAME = MOUNTMSG . -
                                              BIT=EXESV_MOUNTMSG,-
TYPE=<SYS,DYNAMIC>,-
                                              UNIT=Boolean
                           DISMOUMSG - Controls operator notification of volume dismounting
                                              ADDRESS=EXE$GL_MSGFLAGS,-
DEFAULT=0,-;
                            PARAMETER
                                              MAX=1,-
                                              MIN=0 .-
                                              NAME = DISMOUMSG . -
                                              BIT=EXE$V_DISMOUMSG,-
TYPE=<SYS,DYNAMIC>,-
                                              UNIT=Boolean
                            . PAGE
                            .SBTTL SYSTEM LOADABLE CODE PARAMETERS
                     DEFINE THE CONTROL BITS IN SGN$GL_LOADFLAGS
                            $GBLINI GLOBAL
                           SVIELD
                                    SGN. 0. <-
                                     LOADERAPAT,-
                                                                : LOAD ERASE PATTERN GENERATOR
                                                                ; LOAD PROTECTION CHECK ROUTINE
                                     LOADCHKPRT .-
                                     LOADMTACCESS .-
                                                                 : LOAD INSTALLATION ACCESSIBILITY ROUTINE
                           >
                            . IF
                                     NOT_DEFINED GETSYISW
                     DEFINE THE SGNSGL_LOADFLAGS LONGWORD AND ITS INITIAL VALUE.
                            .ALIGN LONG
                                     NDF , PRMSW
                  SGNSGL_LOADFLAGS::
                            .ENDC
                            .LONG
                            .ENDC
                                    ; NOT_DEFINED GETSYISW
                           LOADERAPAT- CONTROLS LOADING OF ALTERNATE ERASE PATTERN GENERATOR
                           PARAMETER
                                              ADDRESS=SGN$GL_LOADFLAGS,-
```

```
F 15
                                         - PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                                                              16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                                                     (1)
PARAMETER
                                                                                                                                                              Page
V04-000
                                                                                            DEFAULT=0,-
                                                                                            MAX=1,-
                                                                                            MIN=0 .-
                                                                                            NAME=LOADERAPT .-
                                                                                            BIT=SGN$V_LOADERAPAT,-
TYPE=<SPECIAL>,-
                                                                                            UNIT=Boolean
                                                                        LOADCHKPRT - CONTROLS LOADING OF ALTERNATE PROTECTION CHECK ROUTINE
                                                                                            ADDRESS=SGN$GL_LOADFLAGS,-
DEFAULT=0,-;
                                                                        PARAMETER
                                                                                            MAX=1,-
                                                                                            MIN=0 .-
                                                                                            NAME = LOAD CHKPRT, -
                                                                                            BIT=SGN$V_LOADCHKPRT,-
TYPE=<SPECIAL>,-
                                                                                            UNIT=Boolean
                                                                        LOADMTACCESS - CONTROLS LOADING OF INSTALLATION SPECIFIC ACCESSIBILITY ROUTI
                                                                        PARAMETER
                                                                                             ADDRESS=SGN$GL_LOADFLAGS,-
                                                                                            DEFAULT=0,-
                                                                                            MAX=1,-
                                                                                            MIN=0,-
                                                                                            NAME=LOADMTACCESS,-
                                                                                            BIT=SGN$V_LOADMTACCESS,-
TYPE=<SPECIAL>,-
                                                                                            UNIT=Boolean
                                                                        . PAGE
                                                                        SBITL TERMINAL DRIVER SYSTEM PARAMETERS
                                                                        DIALUP SUPPORT CONTROL PARAMETERS
                                                                DELTA TIME FOR DIALUP TIMER SCAN
                                                                                            ADDRESS=TTYSGL_DELTA,-
DEFAULT=<100000*100>,-
                                                                        PARAMETER
                                                                                            MIN=100000 .-
                                                                                            NAME = TTY SCANDELTA, -
SIZE = LONG, -
                                                                                            TYPE=<TTY>,-
                                                                                            UNIT=100Ns
                                                                FLAGS FOR DIALUP
                                                                        BIT 0 is 0 => NORMAL, 1 => UNITED KINGDOM
BIT 1 SPECIFIES ALTERNATE MODEM PROTOCOL
```

PARAMETER

ADDRESS=TTY\$GB\_DIALTYP,-DEFAULT=0,-

MIN=0,-MAX=<^XOFF>,-NAME=TTY\_DIALTYPE,-TYPE=<TTY>,-SIZE=BYTE,-

UNIT=Bit-Encoded

Page 50 (1)

```
NOTE ALIGNMENT!
               TERMINAL CANONICAL CHARACTERISTICS
                       DEFAULT SPEED FOR TERMINALS
                                           ADDRESS=TTY$GB_DEFSPEED, -: DEFAULT SPEED FOR TERMINALS AND P
DEFAULT=TT$C_BAUD_9600, -: 9600 BAUD - NO PARITY
                       PARAMETER
                                          MIN=1,-
                                           MAX=16.-
                                           NAME = TTY SPEED , -
SIZE = BYTE , -
                                           TYPE=<TTY>,-
                                           UNIT=Special
                                                                          TT$C_BAUD VALUES
                       DEFAULT RECEIVE SPEED
                                           ADDRESS=TTY$GB_RSPEED, - ; THE RECEIVE SPEED FOR A TERMINAL
                       PARAMETER
                                           DEFAULT=0,-
                                                                         USE THE DEFAULT SPEED
                                           MIN=0,-
MAX=16,-
                                           NAME=TTY_RSPEED,-
                                           SIZE=BYTE .-
                                           TYPE=<TTY>,-
                                           UNIT=Special
                                                                          TT$C_BAUD VALUES AND 0
                       DEFAULT PARITY
                       PARAMETER
                                           ADDRESS=TTY$GB_PARITY, - ; THE PARITY OF THE TERMINALS
                                           DEFAULT=24,-
                                                                        :NO PARITY EIGHT BITS.
                                           MIN=0 .-
                                          NAME = TTY PARITY, -
SIZE = BYTE, -
                                           TYPE=<TTY>,-
                                          UNIT=Special
                       DEFAULT TERMINAL LINE WIDTH
                       PARAMETER
                                           ADDRESS=TTY$GW_DEFBUF,- ; DEFAULT BUFFER SIZE
                                           DEFAULT=80,-
                                           MIN=0.-
                                           MAX=65535.-
                                           NAME = TTY_BUF , -
                                           SIZE=WORD .-
                                           TYPE=<TTY>,-
                                           UNIT=Characters
000C
000C
                       DEFAULT TERMINAL CHARACTERISTICS
0000
                       PARAMETER ADDRESS=TTYSGL_DEFCHAR,-: DEFAULT CHARACTERISTICS
DEFAULT=<<24attsv_page>+ttsm_ttsync+ttsm_wrap+ttsm_lower+ttsm_scope>,-
000C
0000
ŎŎŎĊ
                                           MIN=0,-
                                          NAME = TTY DEFCHAR, -
SIZE = LONG, -
ÖÖÖÖ
                                           TYPE=<TTY>,-
```

ADDRESS=TTY\$GW\_PROT,-

Page

; PROTECTION CLASSES

H 15

PARAMETER

- PARAMETER DESCRIPTORS FOR SYSPARAM

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                           16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                           52
                                                                                                                                   Page
                                                         DEFAULT=<^XOFFFO>,-
MIN=0,-
NAME=TTY_PROT,-
                                                                                                          SYSTEM ONLY
                                                          SIZE=WORD .-
                                                          TYPE=<TTY>,-
                                                         UNIT=Protection
                                                         ADDRESS=TTY$GL_OWNUIC,-
DEFAULT=<^X000T0004>,-
                                  PARAMETER
                                                                                                          OWNER UIC
                                                                                                          SYSTEM OWNER
                                                          MIN=0,-
                                                         NAME=TTY_OWNER,-
SIZE=LONG,-
TYPE=<TTY>-
                                                         UNIT=UIC
                                  DEFAULT TERMINAL CLASS NAME PREFIX
                                                         ADDRESS=TTY$GW_CLASSNAM,-
DEFAULT=<^A/TT7>,-
                                  PARAMETER
                                                          MIN=<^A/AAAA/>,-
                                                         MAX=<^A/ZZZZ/>,-
NAME=TTY_CLASSNAME,-
SIZE=WORD,-
TYPE=<ASCII,TTY>,-
UNIT=Ascii
                                  DEFAULT SILO TIMEOUT VALUE FOR DMF32
                                  PARAMETER
                                                          ADDRESS=TTY$GB_SILOTIME .-
                                                         DEFAULT=8,-
                                                         MIN=0,-

MAX=255,-

NAME=TTY_SILOTIME,-

SIZE=BYTE,-

TYPE=<TTY>,-
                                                         UNIT=Ms
                          DISCONNECTED VIRTUAL TERMINAL TIMEOUT.
                                                         ADDRESS=TTY$GL_TIMEOUT,-
DEFAULT=60*15,-; 15 minute default
                                  PARAMETER
                                                         MIN=0,-
                                                         NAME=TTY_TIMEOUT,-
SIZE=LONG,-
TYPE=<TTY,DYNAMIC>,-
                                                         UNIT=Seconds
                          AUTOBAUD RATE RECOGNITION CHARACTER
                                                          ADDRESS=TTY$GB_AUTOCHAR,-
                                  PARAMETER
                                                         DEFAULT=7,-
                                                                                 : Default is *G (Bell)
                                                         MIN=0.-
MAX=255,-
                                                         NAME = TTY AUTOCHAR, -
SIZE = BYTE, -
                                                          TYPE=<TTY, DYNAMIC>,-
                                                         UNIT=Character
```

VAX/VMS Macro V04-00 [SYS.SRC]SYSPARAM.MAR; 1 53

VC

Page

J 15

- PARAMETER DESCRIPTORS FOR SYSPARAM

SYSGEN PARAMETERS

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                            16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                                           VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                                                                                                            (1)
                                                                                                                                    Page
                                                          SIZE=BYTE,-
TYPE=<RMS,DYNAMIC>,-
                                                          UNIT=Buffers
                          DEFAULT MULTI-BUFFER COUNT FOR RELATIVE FILES
                                   PARAMETER
                                                           ADDRESS=SYS$GB_DFMBFREL,-
                                                          DEFAULT=0,-
MIN=0,-
MAX=127,-
NAME=RMS_DFMBFREL,-
SIZE=BYTE,-
TYPE=<RMS,DYNAMIC>,-
                                                          UNIT=Buffers
                          DEFAULT MULTI-BUFFER COUNT INDEXED FILES
                                   PARAMETER
                                                          ADDRESS=SYS$GB_DFMBFIDX,-
                                                          DEFAULT=0,-
                                                          MIN=0,-
MAX=127,-
                                                          NAME=RMS_DFMBFIDX,-
SIZE=BYTE,-
TYPE=<RMS,DYNAMIC>,-
                                                          UNIT=Buffers
                          DEFAULT MULTI-BUFFER COUNT HASHED
                                   PARAMETER
                                                           ADDRESS=SYS$GB_DFMBFHSH,-
                                                          DEFAULT=0,-
MIN=0,-
MAX=127,-
NAME=RMS_DFMBFHSH,-
SIZE=BYTE,-
                                                          TYPE=<RMS, DYNAMIC>,-
                                                          UNIT=Buffers
                          Default rms Prologue
                                                          ADDRESS = SYS$GB_RMSPROLOG,-
DEFAULT = 0,- ; 0, 2 and 3 are valid, only
                                   PARAMETER
                                                          MIN = 0,-
MAX = 3,-
                                                          NAME = RMS_PROLOGUE,-
SIZE = BYTE,-
TYPE = <RMS,DYNAMIC>,-
                                                          UNIT = Prolog-Lvl
                          Default file extend quantity
                                   PARAMETER
                                                          ADDRESS = SYS$GW_RMSEXTEND,-
DEFAULT = 0,-
                                                          MIN = 0 -
MAX = 65535,-
```

VO

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                            16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                          NAME = RMS_EXTEND_SIZE,-

SIZE = WORD,-

TYPE = <RMS,DYNAMIC>,-

UNIT = Blocks
                          Default file protection
                                                           ADDRESS = SYS$GW_FILEPROT,-
DEFAULT = <^XFA00>,-
                                   PARAMETER
                                                           MIN = 0 -
MAX = < XFFFF>,-
                                                          NAME = RMS_FILEPROT,-
SIZE = WORD,-
TYPE = RMS,-
UNIT = Prot-mask
                          Global buffer quota - This parameter determines the maximum number
                          of global buffers that may be in use in the system at any one time.
                                   PARAMETER
                                                           ADDRESS=SYS$GW_GBLBUFQUO,-
                                                           DEFAULT=1024,-
                                                           MIN=0,-
MAX=32767,-
                                                           SIZE=WORD .-
                                                           NAME = RMS GBLBUFQUO, -
TYPE = < RMS , DYNAMIC>, -
                                                           UNIT=<Gbl bufs>
                2983
2983
2984
2985
2986
2988
2988
2988
                          Network block count - This parameter determines the number of blocks to use for RMS DAP network record-mode transfers.
                          This parameter determines the maximum record size that can be
                          sent over the network.
                                   PARAMETER
                                                           ADDRESS=SYS$GB_DFNBC,-
                                                           DEFAULT=8,-
                                                           MIN=1,-
                                                           MAX=127.
                                                           SIZE=BYTE,-
                                                           NAME=RMS_DFNBC,-
                                                           TYPE=<RMS, DYNAMIC>,-
                                                           UNIT=<Blocks>
                                    . IF
                                               NOT_DEFINED GETSYISW
                 2997
2998
2999
3000
3001
3002
3004
3005
3006
3007
                                    .ALIGN LONG
                            END OF RMS DEFAULT PARAMETERS
                                    .PAGE
.SBTTL
                                               PROCESS QUOTA DEFAULTS AND MINIMA
                                    = .-4
                                    DEFINE
                                               PQL$AL_DEFAULT
                                    .=.+4
.BLKL
                                               PQL$_LENGTH
```

VC

56		
20	54	
	20	

PA

VO4-000 SYSGEN PARAMETERS	PARAMETER V04-000	- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
---------------------------	----------------------	--

16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 [SYS.SRC]SYSPARAM.MAR;1

000C 000C 000C 000C 000C 000C	3008 3009	DEFINE	PQL\$AL_MIN	
0000	3010 3011	.=.+4 .BLKL	PQL\$_LENGTH	
0000	3012 3013	BLKL DEFINE	PQL\$AB_FLAG	
000C	3014 3015	.=.+1	PQL\$_LENGTH	
000C	3016 3017		; NOT_DEFINED GETSYISW	
000C	3018 3019 :			
000C	3020 : 3021 :	DEFINE F	PROCESS QUOTA DEFAULTS AND	MINIMA
000C 000C 000C 000C 000C 000C 000C	3022 3023 3024 3025 3026	PQL	ASTLM,- DEFLT=24,- MINIM=4,- UNT=Ast	AST LIMIT
000C 000C 000C	3028 3029 3030 3031	PQL	BIOLM,- DEFLT=18,- MINIM=4,- UNT=I/O	BUFFERED I/O LIMIT
000C 000C 000C 000C 000C 000C 000C	3033 3034 3035 3036 3037	PQL	BYTLM,- DEFLT=8192,- FLAG=DEDUCTIBLE,- MINIM=1024,- UNT=Bytes	BUFFERED I/O BYTE COUNT LIMIT
000C 000C 000C 000C	3038 3039 3040 3041 3042 3043	PQL	CPULM,- DEFLT=0,- FLAG=DEDUCTIBLE,- MINIM=0,- UNT=10Ms	CPU TIME LIMIT
0000	3044 3045 3046 3047 3048 3049	PQL	DIOLM,- DEFLT=18,- MINIM=4,- UNT=I/O	DIRECT I/O LIMIT
000C 000C 000C 000C	3050 3051 3052 3053 3054	PQL	FILLM,- DEFLT=16,- FLAG=DEDUCTIBLE,- MINIM=2,- UNT=Files	OPEN FILE LIMIT
000C 000C 000C 000C 000C 000C 000C 000	3056 3057 3058 3059 3060	PQL	PGFLQUOTA,- DEFLT=2048,- FLAG=DEDUCTIBLE,- MINIM=512,- UNT=Pages	PAGING FILE QUOTA
000C	3060 3061 3062 3063 3064	PQL	PRCLM,- DEFLT=8,- FLAG=DEDUCTIBLE,-	SUB-PROCESS LIMIT

NBCDEFGHI

MINIM=0,-UNT=Processes TQELM,-DEFLT=8,-FLAG=DEDUCTIBLE,-PQL MINIM=0,-UNT=Timers WSDEFAULT, -DEFLT=100, -MINIM=60, -PQL UNT=Pages,-DYNAMIC\_FLAG=STATIC DEFAULT WORKING SET SIZE - SIZE OF SHELL WORKING SET .IF NOT\_DEFINED GETSYISW
.IF NDF, PRMSW
SGN\$GW\_DFWSCNT==PQL\$GDWSDEFAULT .ENDC ; NOT DEFINED GETSYISW WSQUOTA, - DEFLT=200,-.ENDC PQL MINIM=60,-UNT=Pages WSEXTENT, -DEFLT=200, -MINIM=10, -PQL UNT=Pages ENQLM,-DEFLT=30,-PQL FLAG=DEDUCTIBLE,-MINIM=4,-UNT=Locks JTQUOTA,-DEFLT=1024,-PQL MINIM=0,-UNT=Bytes . PAGE .SBTTL FILE ACP CONFIGURATION DATA File ACP configuration data. These parameters are used whenever an ACP is started up (or, in the case of per volume data, when a volume is mounted).

Number of blocks in bitmap cache.

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                         VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
SYSGEN PARAMETERS
     PARAMETER
                                               ADDRESS=ACP$GW_MAPCACHE,-
                                               DEFAULT=8,-
                                               MIN=1 .-
                                               NAME = ACP_MAPCACHE, -
                                               SIZE=WORD,-
                                               TYPE=<ACP, DYNAMIC>,-
                                               UNIT=Pages
                     Number of blocks in file header cache.
                                               ADDRESS=ACP$GW_HDRCACHE,-
                            PARAMETER
                                               DEFAULT=128,-
                                               MIN=3.-
                                               NAME = ACP_HDRCACHE . -
                                               SIZE=WORD .-
                                               TYPE=<ACP, DYNAMIC> .-
                                               UNIT=Pages
             3140
                     Number of blocks in file system directory data block cache.
                                               ADDRESS=ACP$GW_DIRCACHE,-
                            PARAMETER
                                               DEFAULT=80,-
                                               MIN=2,-
                                               NAME = ACP_DIRCACHE, -
                                               SIZE=WORD .-
                                               TYPE=<ACP, DYNAMIC>,-
             3148
3149
                                               UNIT=Pages
            3150
3151
3152
3153
3154
3155
3157
3158
3159
                     Number of pages in file system directory index cache.
                                               ADDRESS=ACP$GW_DINDXCACHE,-
                            PARAMETER
                                               DEFAULT=25,-
                                               MIN=2,-
                                               NAME = ACP_DINDXCACHE, -
                                               SIZE=WORD,-
                                               TYPE = < ACP, DYNAMIC>, -
                                              UNIT=Pages
             3160
3161
                     ACP working set in pages (0 means maximal)
             3162
3163
                            PARAMETER
                                               ADDRESS=ACP$GW_WORKSET,-
                                               DEFAULT=0,-
             3164
3165
3166
3167
                                               MIN=0,-
                                               NAME = ACP WORKSET . -
                                               SIZE=WORD,-
                                               TYPE = < ACP, DYNAMIC>, -
             3168
                                               UNIT=Pages
                     The following parameters are applied on a per volume basis.
                     Number of cached index file slots
                            PARAMETER
                                               ADDRESS=ACP$GW_FIDCACHE,-
                                               DEFAULT=64,-
                                               MIN=0.-
                                               NAME = ACP_FIDCACHE, -
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                       16-SEP-1984 00:45:38
5-SEP-1984 03:55:49
                                                                                    VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR; 1
                                                     SIZE=WORD,-
TYPE=<ACP,DYNAMIC>,-
                                                      UNIT=File-Ids
      0000C
0000C
0000C
0000C
0000C
0000C
0000C
0000C
                        Number of cached disk extents
                                PARAMETER
                                                      ADDRESS=ACP$GW_EXTCACHE,-
                                                      DEFAULT=64,-
                                                     MIN=0.-
NAME=ACP_EXTCACHÉ,-
SIZE=WORD,-
TYPE=<ACP,DYNAMIC>,-
UNIT=Extents;
                        Maximum fraction of disk to cache in tenths of percent
                                                      ADDRESS=ACP$GW_EXTLIMIT,-
                                PARAMETER
                                                      DEFAULT=100,-
                                                      MIN=0.-
      000C
000C
000C
                                                      MAX=1000,-
               3198
                                                     NAME = ACP_EXTLIMIT, -
SIZE = WORD, - ;
               3199
                                                      TYPE=<ACP, DYNAMIC>,-
       0000
                                                      UNIT=<Percent/10>
      000C
000C
000C
000C
000C
000C
000C
                        Number of quota file entries to cache
                                PARAMETER
                                                      ADDRESS=ACP$GW_QUOCACHE,-
                                                      DEFAULT=64,-
                                                      MIN=0,-
                                                      MAX=-1 .-
                                                      NAME = ACP_QUOCACHE, -
                                                      SIZE=WORD,-
                                                      TYPE=<ACP, DYNAMIC>,-
      000C
000C
000C
000C
                                                      UNIT=Users
                        Default access for system volumes
                                PARAMETER
                                                      ADDRESS=ACP$GW_SYSACC.- ;
      000C
                                                      DEFAULT=8,-
                                                      MIN=0.-
                                                     NAME = ACP_SYSACC ,-
                                                      SIZE=WORD,-
                                                      TYPE=<ACP, DYNAMIC>,-
                                                      UNIT=Directories
                        Maximum number of blocks to read at once for directories.
      000C
000C
000C
000C
000C
                                                      ADDRESS=ACP$GB_MAXREAD,-
                                PARAMETER
                                                      DEFAULT=32,-
                                                     MIN=1,-
MAX=64,-
                                                      NAME = ACP_MAXREAD . -
                                                     SIZE = BYTE .-
                                                      TYPE = <ACP, DYNAMIC>, -
                                                      UNIT=Blocks
```

```
Default window size for system volumes.
                                          ADDRESS=ACP$GB_WINDOW,-;
DEFAULT=7,-;
                       PARAMETER
                                          MIN=1,-
                                          NAME = ACP WINDOW, -
SIZE = BYTE, -
                                          TYPE=<ACP, DYNAMIC>,-
                                          UNIT=Pointers
               Deferred cache writeback enable.
                       PARAMETER
                                          ADDRESS=ACP$GB_WRITBACK,-
                                          DEFAULT=1,-
                                          MIN=0,-
                                          MAX=1 .-
                                          NAME = ACP WRITEBACK, -
SIZE = BYTE, -
000C
000C
000C
                                          TYPE=<ACP, DYNAMIC>,-
                                          UNIT=Boolean
               ACP datacheck enable flags.
000C
000C
000C
                       PARAMETER
                                          ADDRESS=ACP$GB_DATACHK,-
                                          DEFAULT=2,-
                                          MIN=0,-
MAX=3,-
0000
                                          NAME = ACP_DATACHECK, -
SIZE = BYTE, -
0000
                                          TYPE = <ACP, DYNAMIC>,-
0000
000C
                                          UNIT=Bit-mask
0000
0000
               Containing the following flags:
0000
0000
                                NDF . PRMSW
                                                             ; Only for exec version of sysparam
0000
                       SGBLINI GLOBAL
                                ACP.O.<-
<READCHK>-
0000
                       SVIELD
; do datachecks on reads
                                <WRITECHK>-
                                                             : do datachecks on writes
                       .ENDC
               The following parameters apply per ACP.
               ACP base priority
                       PARAMETER
                                          ADDRESS=ACP$GB_BASEPRIO,-
                                          DEFAULT=8,-
                                          MIN=4 -
MAX=31,-
       3287
3288
3289
3290
3291
3292
                                          NAME = ACP_BASEPRIO, -
                                          SIZE=BYTE,-
                                          TYPE=<ACP, DYNAMIC>,-
                                          UNIT=Priority
```

```
16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
- PARAMETER DESCRIPTORS FOR SYSPARAM
                                                                                                                        Page
SYSGEN PARAMETERS
                     : ACP Swap flags
                                                     ADDRESS=ACP$GB_SWAPFLGS,-
DEFAULT=<^B111T>,-
                               PARAMETER
                                                     MIN=0 -
MAX=15,-
                                                     NAME = ACP_SWAPFLGS, -
SIZE = BYTE, - ;
      TYPE=<ACP, DYNAMIC>-
                                                     UNIT=Bit-mask
                                                                          ; swappable, as follows:
                               SGBLINI GLOBAL
                                                                          : Only for exec version of sysparam
                                SVIELD.
                                          ACP, 0, <-
                                          <SWAPSYS>-
                                                                          : /SYSTEM
                                          <SWAPGRP>-
                                                                          : /GROUP
                                          <SWAPPRV>-
                                                                          ; other (private mount)
                                          <SWAPMAG>-
                                                                          : magtape
                                .ENDC
                       XQP memory resident control flag
                                                     ADDRESS=EXE$GL_STATIC_FLAGS,-
DEFAULT=1,-
                               PARAMETER
                                                     MIN=0,-
                                                    MAX=1.-
NAME=ACP XQP RES.-
BIT=EXESV XQP RESIDENT.-
TYPE=<ACP,STATIC>,-
                                                     UNIT=Boolean
                       System disk rebuild flag.
                               PARAMETER
                                                     ADDRESS=EXE$GL_STATIC_FLAGS,-
                                                     DEFAULT=1,-
                                                     MIN=0,-
                                                     MAX=1,-
                                                    NAME=ACP REBLDSYSD.-
BIT=EXE$V_REBLDSYSD.-
TYPE=<ACP.STATIC>,-
                                                     UNIT=Boolean
                                .IIF
                                          NOT_DEFINED GETSYISW,
                                                                          .ALIGN LONG
                               .PAGE
.SBTTL
                                          Job Controller Parameters
                       Default Priority for Job Initiations
                                                     SYS$GB_DEFPRI,-
DEFAULT=4,-
                               PARAMETER
                                                    MIN=1,-

MAX=31,-

NAME=DEFPRI,-

SIZE=BYTE,-

TYPE=<SYS,JBC,DYNAMIC>,-
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM SYSGEN PARAMETERS
                                                 16-SEP-1984 00:45:38 VAX/VMS Macre V04-00 
5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                               UNIT=Priority
                   ; Limit for interactive Jobs
                            PARAMETER
                                                ADDRESS=SYS$GW_IJOBLIM,-
                                                DEFAULT=64,-
                                                MIN=1.-
                                                MAX=1024 .-
                                                NAME=IJOBLIM,-
                                                SIZE=WORD,-
                                                TYPE=<JBC, DYNAMIC>,-
                                                UNIT=Jobs
                     Limit for batch Jobs
                            PARAMETER
                                                ADDRESS=SYS$GW_BJOBLIM,-
                                                DEFAULT=16,-
                                                MIN=0.-
                                                MAX=1024 .-
                                                NAME = BJOBLIM, -
                                                SIZE=WORD,-
                                                TYPE=<JBC, DYNAMIC>,-
                                                UNIT=Jobs
                     Limit for network Jobs
                            PARAMETER
                                                ADDRESS=SYS$GW_NJOBLIM,-
                                                DEFAULT=16,-
                                                MIN=0,-
MAX=1024,-
                                                NAME=NJOBLIM,-
                                                SIZE=WORD,-
                                                TYPE=<JBC, DYNAMIC>,-
                                                UNIT=Jobs
                     Limit for Remote Terminal Jobs
                            PARAMETER
                                                ADDRESS=SYS$GW_RJOBLIM,-
                                                DEFAULT=16,-
                                                MIN=0,-
MAX=254,-
                                                NAME=RJOBLIM, -
                                                SIZE=WORD,-
TYPE=<JBC,DYNAMIC>,-
                                                UNIT=Jobs
                            DEFQUEPRI - Default Queue Priority
                                                ADDRESS=SYS$GB_DEFQUEPRI,-
                            PARAMETER
                                                DEFAULT=4,-
MAX=255,-
                                                MIN=0.-
                                                NAME = DEFQUEPRI, -
TYPE = < JBC, DYNAMIC>, -
                                                UNIT=Priority
```

F 16

62

```
3407
3408
3409
3410
3411
                     MAXQUEPRI - Maximum Queue Priority
                     PARAMETER
                                        ADDRESS=SYS$GB_MAXQUEPRI,-
                                       DEFAULT=4,-
MAX=255,-
                                       MIN=0.-
                                        NAME = MAXQUEPRI, -
                                        TYPE=<JBC, DYNAMIC>,-
                                       UNIT=Priority
                     . PAGE
                     .SBTTL Login Security Parameters
2000
              Number of seconds that a dialup user has in which to enter the system
000C
              password before LOGINOUT goes away
000C
                     PARAMETER
                                        ADDRESS=SYS$GB_PWD_TMO,-
                                        DEFAULT=30,-
                                       MIN=0,-
                                       MAX=255 .-
                                       NAME=LGI_PWD_TMO,-
                                        SIZE=BYTE.
                                        TYPE=<DYNAMIC, LGI>,-
                                       UNIT=Seconds
0000
0000
000C
              Number of retries an interactive user has before the process goes away
0000
0000
                                       ADDRESS=SYS$GB_RETRY_LIM,-
DEFAULT=3,-
                     PARAMETER
0000
0000
                                       MIN=0.-
                                       MAX=255 .-
0000
                                       NAME=LGI_RETRY_LIM,-
0000
0000
                                        SIZE=BYTE .-
0000
                                        TYPE=<DYNAMIC, LGI>,-
0000
                                       UNIT=Tries
000C
0000
0000
              Number of seconds that a user has in which to attempt another login
0000
              before the process goes away
0000
000C
                                       ADDRESS=SYS$GB_RETRY_TMO,-
DEFAULT=20,-
                     PARAMETER
0000
                                       MIN=0,-
MAX=255,
                                       NAME = LGI_RETRY_TMO, -
SIZE = BYTE, -
                                        TYPE=<DYNAMIC, LGI>,-
                                       UNIT=Seconds
              Number of consecutive login failures before LOGINOUT begins evasive action
                     PARAMETER
                                        ADDRESS=SYS$GB_BRK_LIM,-
                                       DEFAULT=5,-
                                       MIN=0,-
MAX=255,-
```

```
- PARAMETER DESCRIPTORS FOR SYSPARAM
SYSGEN PARAMETERS
                                                                                  VAX/VMS Macro V04-00
[SYS.SRC]SYSPARAM.MAR:1
                                                                                                                              64
                                                                                                                       Page
                                                    NAME=LGI_BRK_LIM,-
SIZE=BYTE,-
TYPE=<DYNAMIC,LGI>,-
                                                    UNIT=Failures
                        Number of seconds that a suspect must be free of login failures before it is taken off the suspect list
                                PARAMETER
                                                    ADDRESS=SYS$GL_BRK_TMO,-
DEFAULT=300,-
                                                    MIN=0.-
                                                    MAX=-1 -
                                                    NAME=LGI_BRK_TMO,-
SIZE=LONG,-
TYPE=<DYNAMIC,LGI>,-
                                                    UNIT=Seconds
                        Number of seconds that LOGINOUT should practice evasive action on an intruder
                                                    ADDRESS=SYS$GL_HID_TIM,-
DEFAULT=300,-
                                PARAMETER
                                                    MIN=0.-
                                                    MAX=-1 .-
                                                    NAME=LGI_HID_TIM,-
SIZE=LONG,-
                                                    TYPE=<DYNAMIC, LGI>,-
                                                    UNIT=Seconds
                                . PAGE
                                .SBTTL Cluster Parameters
       000C
000C
000C
000C
                               VAXCLUSTER - Controls loading of cluster code
                                          0: Never load
1: Load if SCSLOA is being loaded
                                          2: Always load (and also load SCSLOA)
                               PARAMETER
                                                    ADDRESS=CLUSGB_VAXCLUSTER, -
                                                    DEFAULT=1,-
MAX=2,-
       000C
                                                    MIN=0.-
                                                    NAME = VAXCLUSTER, -
                                                    SIZE=BYTE,-
                                                    TYPE=<CLUSTER>,-
                                                    UNIT=Coded-value
       000C
000C
000C
000C
000C
                        Quorum for an operable cluster
                               PARAMETER
                                                    ADDRESS=CLU$GW_QUORUM,-
                                                    DEFAULT=1,-
                                                    MIN=1,-
                                                    MAX=32767,-
                                                    NAME = QUORUM, -
                                                    SIZE=WORD,-
```

```
MAX=32767,-
NAME=QDSKINTERVAL,-
                                       SIZE=WORD,-
TYPE=<CLUSTER>,-
                                       UNIT=Seconds
         Define a parameter which determines the device allocation class for this system. The device allocation class is used to derive a common
         lock resource name for multiple access paths to the same device.
                                       ADDRESS=CLU$GL_ALLOCLS, - NAME=ALLOCLASS, -
                  PARAMETER
                                       TYPE=<CLUSTER>, -
                                       DEFAULT=0, -
                                       MIN=0. -
MAX=255, -
                                       UNIT=Pure-number
         Lock manager directory system weight. Determines portion of lock manger directory entires which will be handled by this system.
3601
                  PARAMETER
                                       ADDRESS=CLU$GW_LCKDIRWT,-
DEFAULT=1,-
                                       MIN=0.-
                                       MAX=255 .-
                                       NAME=LOCKDIRWT,-
                                       SIZE=WORD .-
                                       TYPE=<CLUSTER>,-
                                       UNIT=Pure-number
3609
3611
         Define a parameter which tells us whether or not this system is tailored (i.e., has a library disk). This is the right way to determine tailoring
         now that many different system disks can be tailored.
3614
3615
                                       ADDRESS=SGN$GB_TAILORED,-
DEFAULT=0,-
                  PARAMETER
                                       MAX=1,-
                                       MIN=0,-
                                       NAME=TAILORED .-
                                       SIZE=BYTE,-
                                       TYPE=<SYS>,-
                                       UNIT=Boolean
                  . IF
                            NOT_DEFINED GETSYISW
         WORK STATION FLAGS.
                  . ALIGN
                            LONG
      EXESGL_WSFLAGS::
                            NDF , PRMSW
                                                                Work station SYSGEN flags
                 .ENDC
                               NDF , PRMSW
                  .LONG
                            : NOT_DEFINED GETSYISW
```

```
SVIELD EXE 0. <-
                                                                   ; DEFINITION FOR EXESGL_DYNAMIC_FLAGS ; Reserve a window for OPAO
                        WS_OPAO -
                                              If set reserve the first 24 scan lines for an OPAO window
                                             ADDRESS=exe$gl_wsflags,-;
DEFAULT=0,- ;
                         PARAMETER
                                              MAX=1,-
                                              MIN=0.-
                                             NAME=WS_OPAO.-;
BIT=EXESV_OPAO.-;
TYPE=<DYNAMIC.SYS>.-;
UNIT=Boolean
                 Define eight parameters which are used to pass information to the system
                startup procedure (STARTUP.COM).
                                             ADDRESS=SGN$GB_STARTUP_P1,-
DEFAULT=<^A/ />,-
                         PARAMETER
                                              MIN=<^A/
                                                             1>,-
                                              MAX=<^A/ZZZZ/>,-
                                              NAME = STARTUP_P1, -
                                              SIZE=LONG,-
                                             TYPE=<ASCII,SYS>,-
UNIT=Ascii
                         PARAMETER
                                              ADDRESS=SGN$GB_STARTUP_P2,-
                                                                - />,-
                                              DEFAULT=<^A/
                                              MIN=<^A/
                                                             1>,-
                                             MAX=<^A/ZZZZ/>,-
NAME=STARTUP_P2,-
                                              SIZE=LONG,-
TYPE=<ASCII,SYS>,-
                                              UNIT=Ascii
                                              ADDRESS=SGN$GB_STARTUP_P3,-
                         PARAMETER
                                              DEFAULT=<^A/
                                                                - />,-
                                              MIN=<A/
                                                             1> .-
                                             MAX=<^A/ZZZZ/>,-
NAME=STARTUP_P3,-
                                             SIZE=LONG,-
TYPE=<ASCII,SYS>,-
                                              UNIT=Ascii
                                              ADDRESS=SGN$GB_STARTUP_P4,-
DEFAULT=<^A/ />,-
                         PARAMETER
                                                                - />,-
                                              MIN=<^A/
                                                             1>,-
                                             MAX=<^A/ZZZZ/>,-
NAME=STARTUP_P4,-
                                             SIZE=LONG,-
TYPE=<ASCII,SYS>,-
                                              UNIT=Ascii
                                              ADDRESS=SGN$GB_STARTUP_P5,-
DEFAULT=<^A/ />,-
                         PARAMETER
                                              MIN=<^A/
                                                             1> .-
                                             MAX=<^A/ZZZZ/>,-
NAME=STARTUP_P5,-
```

PARAMETER	
V04-000	

- PARAMETER DESCRIPTORS SYSGEN PARAMETERS	FOR SYSPARAM	16-SEP-1984 5-SEP-1984	00:45:38 03:55:49	VAX/VMS Macro V04-00 [SYS.SRC]SYSPARAM.MAR;1	Page 6	68
000C 3692 000C 3693 000C 3694 000C 3695 000C 3696 000C 3697	PARAMETER	SIZE=LONG,- TYPE= <ascii,s UNIT=Ascii ADDRESS=SGN\$( DEFAULT=&lt;^A/ MIN=&lt;^A/ MAX=&lt;^A/ZZZZ</ascii,s 	GB_STARTUP	_P6,-		
000C 3699 000C 3700 000C 3701 000C 3702 000C 3703 000C 3704 000C 3705	PARAMETER	MIN= <a a="" zzzz<br="">MAX=<a zzzz<br="">NAME=STARTUP SIZE=LONG,- TYPE=<ascii,s UNIT=Ascii ADDRESS=SGNS DEFAULT=<a min="&lt;A/A/ZZZZZZZZZZZZZZZZZZZZZZZZZZZZZZZZZZ&lt;/td"><td>_P6,- SYS&gt;,- GB_STARTUP /&gt;,- /&gt;,-</td><td>_P7,-</td><td></td><td></td></a></ascii,s </a></a>	_P6,- SYS>,- GB_STARTUP />,- />,-	_P7,-		
000C 3695 000C 3696 000C 3698 000C 3699 000C 3700 000C 3701 000C 3702 000C 3703 000C 3705 000C 3706 000C 3707 000C 3710 000C 3711 000C 3712 000C 3713 000C 3715 000C 3716 000C 3716 000C 3718 000C 3718 000C 3719 000C 3720 000C 3721	PARAMETER	MIN=<^A/ MAX=<^A/ZZZZ NAME=STARTUP SIZE=LONG,- TYPE= <ascii,s address="SGN\$" default="&lt;^A/" max="&lt;^A/ZZZZ" min="&lt;^A/" name="STARTUP" size="LONG,-" type="&lt;ASCII,S" unit="Ascii&lt;/td"><td>/&gt;-</td><td>_P8,-</td><td></td><td></td></ascii,s>	/>-	_P8,-		
000C 3717 000C 3718 000C 3719 000C 3720	.IF NOT_D	UNIT=Ascii	515>,-			
000C 3721 000C 3722 000C 3723 000C 3724 000C 3725 000C 3726 000C 3727 000C 3728 000C 3729 000C 3730 000C 3731 000C 3732	.PAGE .SBTTL COMPU .ALIGN LONG	TED VALUES	PAGE	S REQUIRED FOR SHELL		
000C 3727 000C 3728 000C 3729	DEFINE SWP\$GI	M_BAKPTE	: PHD	PAGES FOR BAK+WSLX+LCK+VAL		
000C 3730 000C 3731 000C 3732	DEFINE SWP\$G	W_EMPTPTE	EMPT	Y PHDPAGES		
000C 3733 000C 3734 000C 3735	DEFINE SWP\$GI	W_WSLPTE	: PHD	PAGES FOR FIXED+WSL+PST		
000C 3736 000C 3737 000C 3738	DEFINE SWP\$GI	B_SHLP1PT	: P1 P	AGE TABLES REQUIRED FOR SHE	ELL	
000C 3739 000C 3740	.BYTE 0		; SPAR	E		
000C 3741 000C 3742 000C 3743	DEFINE SWP\$G	L_BSLOTSZ	: SIZE	OF BALANCE SLOT		
000C 3744 000C 3745	DEFINE SWP\$G	L_MAP	SWAP	PER MAP POINTER		
000C 3746 000C 3747 000C 3748	DEFINE SWPSG	L_PHDBASVA	; BASE	ADDRESS OF PHD WINDOW		

PARAME	TER
V04-00	

- PARAMETER DESCRIPTORS SYSGEN PARAMETERS	FOR SYSPARAM 16-SEP-1984 5-SEP-1984	00:45:38 VAX/VMS Macro V04-00 Page 69 03:55:49 [SYS.SRC]SYSPARAM.MAR;1 (1)
000C 3749	.LONG 0	
000C 3750 000C 3751 000C 3752 000C 3753	DEFINE SGNSGL_PHDAPCNT O	TOTAL SHELL HEADER PAGES
000C 3754 000C 3755 000C 3756	DEFINE SGNSGL_PHDLWCNT	COUNT OF LONGWORDS IN PHD
000C 3757 000C 3758 000C 3759	DEFINE SGN\$GL_P1LWCNT	COUNT OF LW TO END OF P1 PAGETABLE
000C 3760 000C 3761 000C 3762	DEFINE SGNSGL_PHDPAGCT	TOTAL PHD PAGES LESS PAGE TABLES
000C 3763 000C 3764 000C 3765	DEFINE SGNSGL_PTPAGCNT .LONG 0	: TOTAL PAGE TABLE COUNT
000C 3766 000C 3767 000C 3768	DEFINE MMG\$GL_CTLBASVA 0	BASE ADDRESS IN CONTROL REGION
000C 3769 : 000C 3770 : 000C 3771 ;	THE FOLLOWING TWO CELLS MUST	BE ADJACENT
000C 3772 000C 3773 000C 3774 000C 3775	DEFINE EXESAL STACKS LONG SWPSA RSTK DEFINE EXESGE_INTSTK LONG 0	: ARRAY OF KERNEL MODE SYSTEM SPACE STACKS : SWAPPER STACK (ADJACENT TO NULL STACK) : BASE OF INTERRUPT STACK
000C 3776 : 000C 3777 : 000C 3778 :	THE PRECEDING TWO LONG WORDS	MUST BE ADJACENT.
000C 3779 000C 3780 000C 3781	DEFINE MMG\$GL_GPTBASE .LONG 0	GLOBAL PAGE TABLE BASE ADDRESS
000C 3781 000C 3782 000C 3783 000C 3784 000C 3785	DEFINE MMG\$GL_GPTE	: BASE ADDRESS OF SPT PTES FOR GPT : PAGES
000C 3785 000C 3786 000C 3787 000C 3788	DEFINE MMG\$GL_MAXGPTE .LONG 0	: HIGHEST GPTE ADDRESS
000C 3789 000C 3790 000C 3791	DEFINE MMG\$GL_MAXSYSVA DEFINE MMG\$GL_FRESVA LONG 0	: HIGHEST SYSTEM VA (+1) : SYNONYM
000C 3793	DEFINE MMG\$GL_SPTBASE .LONG 0	: BASE ADDRESS OF SPT (VIRTUAL)
000C 3794 000C 3795 000C 3796 000C 3797 000C 3798	DEFINE MMG\$GL_SPTLEN 0	: LENGTH OF SYSTEM PAGE TABLE
nnnr	DEFINE MMG\$GL_SYSPHD .LONG 0	: VA OF SYSTEM PHD
000C 3800 000C 3801 000C 3802 000C 3803 000C 3804 000C 3805	DEFINE MMG\$GL_SYSPHDLN 0	SIZE OF SYSTEM PHD IN BYTES
000C 3804 000C 3805	DEFINE SWPSGL_BALBASE	; BASE VA OF BALANCE SLOTS FOR

DADAMETED
PARAMETER VQ4-000
VIOY - 000
VU4-000

NAME OF TAXABLE PARTY OF TAXABLE PARTY.							
- PARAMETEI	R DESCRIPTORS AMETERS	FOR SYS	B 1 PARAM 165	-SEP-1984 -SEP-1984	00:45: 03:55:	38 VAX/VMS Macro VO4 49 ESYS.SRCJSYSPARA	4-00 Pag M.MAR;1
0000	3806	.LONG	0		; P	ROCESS HEADERS	
000C	3808 3809	DEFINE .LONG	SWP\$GL_BALS	PT	; B	ASE VA IN SPT FOR MAI	PPING BALANCE
000C	3811 3812 3813	DEFINE .LONG	MMG\$GL_SBR		; s	YSTEM BASE REGISTER	
0000	3814 3815	DEFINE .LONG	MMG\$GL_NPAGE	EDYN	; v	A OF NON-PAGED POOL	
0000	3817 3818 3819	DEFINE .LONG	MMG\$GL_NPAGE	NEXT	; N	EXT VA FOR NON-PAGED	POOL EXTENSION

PDA

70 (1)

000C 3811 000C 3812 000C 3813	DEFINE MMG\$GL_SBR	: SYSTEM BASE REGISTER
000C 3814	DEFINE MMG\$GL_NPAGED	YN : VA OF NON-PAGED POOL
000C 3816 000C 3817 000C 3818	DEFINE MMG\$GL_NPAGNE	XT : NEXT VA FOR NON-PAGED POOL EXTENSION
000C 3819 000C 3820 000C 3821	DEFINE MMG\$GL_IRPNEX	NEXT VA FOR IRP LIST EXTENSION
000C 3822 000C 3823	DEFINE MMG\$GL_LRPNEX	NEXT VA FOR LRP LIST EXTENSION
000C 3825 000C 3826 000C 3827	DEFINE MMG\$GL_SRPNEX	NEXT VA FOR SRP LIST EXTENSION
000C 3828 000C 3829 000C 3830	DEFINE MMG\$GL_PAGEDY	N : VA OF PAGED POOL
000C 3831 000C 3832 000C 3833 000C 3834 000C 3835 000C 3836	DEFINE MMG\$GL_MAXPFN	MAXIMUM PFN FOR SYSTEM
000C 3834 000C 3835 000C 3836	DEFINE MMG\$GL_MINPFN	: MINIUMUM PFN IN PFN DATABASE
00C 3838 00C 3839	DEFINE MMG\$GL_MAXMEM	: HIGHEST PFN MAPPED BY SYSBOOT : INCLUDES PAGES NOT IN PFN DATABASE
000C 3841 000C 3842	DEFINE EXESGL_RPB	: VIRTUAL ADDRESS OF RESTART PARAMETER BLK
00C 3844 00C 3845	DEFINE BOOSGL_SPTFRE	L : LOWER VPN OF SPT FREE AREA
000C 3847	DEFINE BOOSGL_SPTFRE	H : HIGHER VPN OF SPT FREE AREA
000C 3849 000C 3850 000C 3851 000C 3852	DEFINE EXESGL_SCB	VIRTUAL ADDRESS OF SCB
000C 3852 000C 3853	DEFINE EXESGL_ARCHFL	AG : ARCHITECTURAL FLAGS (BITS DEFINED ; BY SARCDEF

: 16 BYTES OF DATA ABOUT THE CPU : 4 BYTES FOR SID, REST CPU SPECIFIC

; SIZE OF PFN DATA BASE IN BYTES

; CPU TYPE READ FROM SID

DEFINE EXESGB CPUDATA

NDF , PRMSW

EXESGB\_CPUTYPE

DEFINE BYTE

. IF

PDA VO4

```
PFN$C_WORD_LEN == 18
PFN$C_LONG_LEN == 22
.ENDC
                                                                  PFNSGB LENGTH
PFNSC_WORD_LEN
                                                                                                                               ; Number of bytes per page in PFN data base ; Defaults to word length FLINK and BLINK
                                               DEFINE
                                                .BYTE
                                               DEFINE
                                                                   MMG$GW_BIGPFN
                                                                                                                               ; flag to indicate size of PFN FLINK, BLINK
                                                . WORD
                                                                                                                               ; word for historical reasons
ŎŎŎĊ
                                                                  EXESGW_PGFL_FID
                                               DEFINE
                                                                                                                               : FILE ID OF PAGEFILE.SYS
: IF FILE IS IN PAGE FILE
000C
                                                . WORD
000C
000C
000C
000C
                                                                                                                                  LONWORD ALIGN POINTERS
BASE OF PFN POINTERS
ADDRESS OF PAGE TABLE ENTRY
BACKING STORE ADDRESS
                                               ALIGN
DEFINE
                                                                  PFNSA_BASE
L,PTE
L,BAK
                                              PFNALC
PFNALC
PFNALC
PFNALC
                                                                                                                           REFERENCE COUNT
FORWARD LINK
ALSO USED AS GLOBAL SHARE COUNT
BACK LINK
ALSO USED AS WORKING SET LIST INDEX
SWAP IMAGE VIRTUAL BLOCK OFFSET
STATE OF PAGE
                                                                  W.REFCNT
                                                                  x,<fLINK,-
SHRCNT>
PFNALC
                                                                  x, <BLINK, -
                                                                   WSLX>
                                                                  W.SWPVBN
B.STATE
B.TYPE
                                              PFNALC
PFNALC
PFNALC
                                                                                                                                   NAME OF STARTUP COMMAND FILE DEFAULT VALUE ALLOW FOR 31 BYTES + COUNT
                                                                   EXESGT_STARTUP
/SYSSSTSTEM:STARTUP.COM/;
                                                .ASCIC
                                                                   <32-<.-EXESGT_STARTUP>> ;
                                                .BLKB
                                                                                                                                    IF EXEC VERSION
SIZE OF SYSTEM PARAMETERS
                                                                   NDF . PRMSW
                          EXESC_SYSPARSZ == . - EXESA_SYSPARAM
                                                .PSFCT
                                                                  $$$918,LONG
                                                . LONG
                                                                                                                                    FLAG TO MARK END
                                                .ENDC
                                                . PAGE
                                                . SUBTITLE
                                                                                      MMG$GL_PGDCOD
                                                                                                                              Boundary of pageable exec
                                 The cells in this module between the definition of EXE$C_SYSPARSZ and the definition of BOO$C_SYSPARSZ are used for communication between SYSBOOT and SYS.EXE without interference from the SYSGEN USE and WRITE commands. SYSBOOT uses BOO$C_SYSPARSZ as the size of the parameter area. SYSGEN uses EXE$C_SYSPARSZ as its size constant and so SYSGEN commands do not affect the contents of cells that follow the definition of
EXESC_SYSPARSZ.
                                 The cell called MMG$GL_PGDCOD contains the address of the boundary between the nonpaged and pageable exec routines. This cell is used by both INIT and SYSBOOT. It is initialized by SYSBOOT to point to the beginning of the second page of patch area that lies between nonpaged and pageable exec routines. If it is necessary to add another page of nonpaged patch space, then this cell (from BOO$GL_PGDCOD in SYSBOOT) and the first longword of the descriptor for the nonpaged read-only patch area must have 512 added to their contents.
```

Page 72 (1)

```
.PSECT
                  $$$917A
         DEFINE
                            MMG$GL_PGDCOD : CELL THAT CONTAINS BOUNDARY PAT$GL_EXP_NPG2 ; (SYNONYM)
         .LONG
         . IF
                  NDF , PRMSW
BOOSC_SYSPARSZ == . - EXESA_SYSPARAM
                                              ; SIZE OF PARAMETER AREA READ BY SYSBOOT
   Bound pagable exec code to page boundary and define starting virtual address of this region.
         .PSECT
                  Y$$$BEGIN_PAGEDCODE,PAGE
         .ENDC
         .ENDC
                            ; NOT_DEFINED GETSYISW
 Terminate the definition of the macro
         .ENDM
                  SYI_GENERATE_TABLE
  Invoke the macro just defined (if this isn't getsyi)
                  NOT_DEFINED GETSYISW, SYI_GENERATE_TABLE
         .IIF
```

PRM B SIZE .=BAS...+PRM\$B\_SIZE

B\_POS

BYTE

PRM

0000181A

01

181B

SET FIELD LONG

```
- PARAMETER DESCRIPTORS FOR SYSPARAM CONTROL PARAMETERS
                                                                          16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1
                                                                                                                                                           Page
0000181B
                181B
181B
                                               .=BAS...+PRM$B_POS
         OD
                                               BYTE EXESV BUGREDOOT
                                              .=BAS ... +PRMSL_FLAGS
00001816
                                              TYP...=0
.IRP TYPNAM, <DYNAMIC, SYS>
TYP...=TYP...!PRM$M_'TYPNAM
00000000
                                              .IF NB EXESV_BUGREBOOT ; DEFINE PRMS
.IF EQ PRMSM_'TYPNAM-PRMSM_DYNAMIC
.IF IDN EXESGL_DEFFLAGS.EXESGL_DEFFLAGS
PRMSM_DYNFLAGS == PRMSM_DYNFLAGS!<1@EXESV_BUGREBOOT>
.ENDC
.ENDC
.ENDC
                                                                                                               ; DEFINE PRMSM_DYNFLAGS
                                              .ENDR
TYP...=TYP...!PRM$M_DYNAMIC
00000001
00002000
                                              PRM$M_DYNFLAGS == PRM$M_DYNFLAGS!<1@EXE$V_BUGREBOOT>
00000041
                                              TYP...=TYP...!PRM$M_SYS ;
00000041
00001838
                                               .LONG TYP ...
                                                                                                     REPOSITION LOCATION COUNTER
BACK TO NORMAL PSECT
RESTORE LOCATION COUNTER
                                               .=SAV...
.PSECT $$$917A,PAGE
         00000194
194 0194
0194
00000194
                                               .=PRMSAV...
```

0194

PDI

74 (1)

PARAMETER V04-000 - PARAMETER DESCRIPTORS FOR SYSPARAM
MMG\$GL\_PGDCOD Boundary of pageable exec 5-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1

03F0 3953 03F0 3954

.IIF NOT\_DEFINED GETSYISW, .END ; PREFIX FILE, IF GETSYISW

Page 75 (1)

PARAMETER Symbol table	- PARAMETER DESCRIPTORS FOR SYSPARAM 16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 ESYS.SRCJSYSPARAM.MAR;1	Page 76
ACP\$GB BASEPRIO ACP\$GB DATACHK ACP\$GB MAXREAD ACP\$GB WINDOW ACP\$GB WINDOW ACP\$GB WINDOW ACP\$GB WINDOW ACP\$GB WINDOW ACP\$GB WINTBACK ACP\$GW DINDXCACHE ACP\$GW DINCACHE ACP\$GW FIDCACHE ACP\$GW FIDCACHE ACP\$GW HAPCACHE ACP\$GW WAPCACHE ACP\$GW WAPCACHE ACP\$GW WORKSET BAS BIT BOO\$A PRMBLK BOO\$A PRMBLK BOO\$A PRMBLK BOO\$GL SPTFREL CLU\$GB QDISK CLU\$GB QDISK CLU\$GB WAXCLUSTER CLU\$GW LCKDIRWT CLU\$GW QDSKINTERVAL CLU\$GW QDSKINTERVAL CLU\$GW QDSKINTERVAL CLU\$GW QOORUM CLU\$GW QOORUM CLU\$GW QOORUM CLU\$GW QOORUM CLU\$GW QOORUM CLU\$GW POTES DEDUCTIBLE EXE\$AL STACKS EXE\$A SYSPARAM EXE\$GB CPUTYPE EXE\$GL ARCHFLAG EXE\$GL TITABL EXE\$GL ARCHFLAG EXE\$GL ARCHFLAG EXE\$GL TODR EXE\$GL TODR EXE\$GL TODR EXE\$GL TODR EXE\$GL STATIC FLAGS EXE\$GL TODR EXE\$GL TO	X	

PARAMETER Symbol table	- PARAMETER DESCRIPTORS FOR SYSPARAM	16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 ESYS.SRCJSYSPARAM.MAR;1	Page 77
MMG\$GL MAXMEM MMG\$GL MAXPFN MMG\$GL MAXSYSVA MMG\$GL MINPFN MMG\$GL NPAGEDYN MMG\$GL NPAGEDYN MMG\$GL PAGEDYN MMG\$GL PAGEDYN MMG\$GL PHYPGCNT MMG\$GL SBR MMG\$GL SPTBASE MMG\$GL SPTBASE MMG\$GL SYSPHDLN MMB\$GL SYSPHDLN MPW\$GW BIGPFN MPW\$GW HILIM MPW\$GW H	00000378 R 02	= 00000048 = 00000056 = 000399FD = 0000004A = 00000049 = 000033FD = 000048FD = 000048FD = 000049FD = 000068FD = 000068FD = 00006FFD = 000006FD = 000006FD = 000006FD = 000004ED = 000006FD = 000006FD = 0000006B	

PARAMETER Symbol table	- PARAMETER DESCR	RIPTORS FOR SYSPARAM 1	6-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1	Page	78
OPS MOVH OPS MOVH OPS MOVH OPS MOVP OPS MOVTC OPS MOVTC OPS MULD2 OPS MULD3 OPS MULD3 OPS MULF3 OPS MULF3 OPS MULF3 OPS MULH3 OPS MULH3 OPS MULH3 OPS POLYF OPS POLYF OPS SUBD2 OPS SUBD2 OPS SUBD2 OPS SUBD3 OPS SUBD4 OPS SUBD4 OPS TSTD OPS TSTF OP	= 000050FD = 00000034 = 0000002E = 00000065 = 00000044 = 00000045 = 0000045FD = 000065FD = 0000055FD = 0000055FD = 00000055 = 0000002A = 0000003BB = 00000042B = 00000042B = 00000042B = 00000042FD = 00000053FD = 0000053FD = 0000053FD = 0000053FD = 0000053FD = 000003BC R 000003BC R 0000003BC R 000003BC R 000003BC R 000003BC R 000003BC R 000003BC R 0000003BC R 0000003BC R 0000003BC R 0000003BC R 0000003BC R 0000000000 R 000000000 R 00000000 R 000000000 R 0000000000	PQL\$GDDIOLM PQL\$GDFILLM PQL\$GDFILLM PQL\$GDFILLM PQL\$GDFILQUOTA PQL\$GDPRCLM PQL\$GDWSEXTENT PQL\$GDWSQUOTA PQL\$GMSTLM PQL\$GMSTLLM PQL\$GMFILLM PQL\$GMFILLM PQL\$GMFILLM PQL\$GMFILLM PQL\$GMSDEFAULT PQL\$GMWSDEFAULT PQL\$GMWSDEFAULT PQL\$GMWSDEFAULT PQL\$GMWSDEFAULT PQL\$GMWSQUOTA PQL\$GMWSQUOTA PQL\$-BIOLM PQL\$-ENGTH PQL\$-FILLM PQL\$-FILM PQL\$-FILLM PQL\$-FILM PQL\$-FILLM PQL\$-FILLM PQL\$-FILLM PQL\$-FILLM PQL\$-FILLM PQL\$-FILMM PQL\$-FILMM PQL\$-FILMM PQL\$-FILMM PQL\$-FILMM PQL\$-FILMM PQL\$-F	*******  *******  *******  *******  ****		

PARAMETER Symbol table	- PARAMETER DESCRIPTORS FOR SYSPARAM 16-SEP-1984 00:45:38 VAX/VMS Macro V04-00 5-SEP-1984 03:55:49 [SYS.SRC]SYSPARAM.MAR;1	Page 79 (1)
PRMSM_ASCII PRMSM_CLUSTER PRMSM_DYNAMIC PRMSM_DYNFLAGS PRMSM_JBC PRMSM_MEG PRMSM_NEG PRMSM_NEG PRMSM_NEG PRMSM_SPECIAL PRMSM_SYSES PRMSM_SYSEN PRMSM_SYSEN PRMSM_TITY PRMST_UNIT PRMSAV PRMSU SAV SCHSGL_AWSTIME SCHSGL_FFRATL SCHSGL_PFRATL SCHSGL_PFRATL SCHSGL_PFRATL SCHSGL_PFRATL SCHSGL_WSINC SCHSGL_WSINC SCHSGL_WSINC SCHSGL_WSINC SCHSGW_AWSMIN SCHSGW_LONGWAIT SCHSGW_IOTA SCHSGW_IOTA SCHSGW_GUAN SCHSGW_SWPFAIL SCSSGB_PANOPOLL SCSSGB_PANOPOLL SCSSGB_PANOPOLL SCSSGB_PANOPOLL SCSSGB_PANOPOLL SCSSGB_PANOPOLL SCSSGB_SYSTEMID SCSSGB_PAPODLINT SCSSGW_PAPODLINT SCSSGW_PASTMOUT SCSSGW_PAPODLINT SCSSGW_PAPODL	= 00000000	

PARAMETER Symbol table	- PARAMETER	DESCRIPTORS	FOR SYSPARAM 16-SEP-198	4 00:45:38 VAX/VMS Macro V 4 03:55:49 [SYS.SRC]SYSPAR	04-00 Page 80 AM.MAR;1 (1
GGNSGL VMSD4 GGNSGW CTLIMGLIM GGNSGW CTLPAGES GGNSGW CTLPAGES GGNSGW GBLSECNT GGNSGW GBLSECNT GGNSGW HAXPROOT GGNSGW MAXPROOT GGNSGW MAXPROOT GGNSGW MAXPSTOT GGNSGW MAXPSTOT GGNSGW PAGFILOT GGNSGW POPAGES GGNSGW SWPFILES GGNSGW SWPFILE GGNS	******  ******  ******  ******  ******  ****	**************************************	SYS\$GW_NJOBLIM SYS\$GW_RJOBLIM SYS\$GW_RMSEXTEND TT\$C_BAUD_9600 TT\$M_LOWER TT\$M_SCOPE TT\$M_SCOPE TT\$M_TTSYNC TT\$M_WRAP TT\$V_PAGE TT2\$M_AUTOBAUD TT2\$M_EDITING TTY\$GB_AUTOCHAR TTY\$GB_DEFSPEED TTY\$GB_AUTOCHAR TTY\$GB_TALTYP TTY\$GB_PARITY TTY\$GB_TSILOTIME TTY\$GL_DEFCHAR2 TTY\$GL_DEFCHAR2 TTY\$GL_DEFCHAR2 TTY\$GL_DEFDORT TTY\$GL_DELTA TTY\$GL_DELTA TTY\$GL_TIMEOUT TTY\$GW_ALTALARM TTY\$GW_ALTALARM TTY\$GW_ALTALARM TTY\$GW_CLASSNAM TTY\$GW_DEFBUF TTY\$GW_DEFBUF TTY\$GW_TYPAHDSZ TYP	******* X 03  ******* X 03	

Page

### ! Psect synopsis !

	PSECT name	Allocation	PSECT No.	Attributes				
Section of the last of the las	*ABS . \$ABS\$ \$\$\$917A \$\$\$918	00000000 ( 0.) 00000000 ( 0.) 000003F0 (1008.) 00003330 (13104.)	00 ( 0.) 01 ( 1.) 02 ( 2.) 03 ( 3.)	NOPIC USR NOPIC USR NOPIC USR NOPIC USR	CON ABS CON REL CON REL	LCL NOSHR NOE) LCL NOSHR E) LCL NOSHR E) LCL NOSHR E)	E RD	NOWRT NOVEC BYTE WRT NOVEC BYTE WRT NOVEC PAGE WRT NOVEC LONG

### Performance indicators !

Phase	Page faults	CPU Time	<b>Elapsed Time</b>
Initialization Command processing	129	00:00:00.08	00:00:01.67
Pass 1	123 1666	00:02:23.00	00:07:39.40
Symbol table sort Pass 2	1107	00:00:02.05	00:00:05.67
Symbol table output Psect synopsis output	5	00:00:00.37	00:00:01.43
Cross-reference output Assembler run totals	2944	00:00:00.00	00:00:00.00 00:09:16.17

The working set limit was 3150 pages.
540912 bytes (1057 pages) of virtual memory were used to buffer the intermediate code.
There were 80 pages of symbol table space allocated to hold 1319 non-local and 0 local symbols.
6707 source lines were read in Pass 1, producing 116 object records in Pass 2.
302 pages of virtual memory were used to define 146 macros.

! Macro library statistics !

#### Macro library name

PARAMETER Psect synopsis

\_\$255\$DUA28:[SYS.OBJ]LIB.MLB;1
\_\$255\$DUA28:[SYSLIB]STARLET.MLB;2
TOTALS (all libraries)

Macros defined

11


1049 GETS were required to define 11 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$: PARAMETER/OBJ=OBJ\$: PARAMETER MSRC\$: PRMSW/UPDATE=(ENH\$: PRMSW) + MASD\$: [EMULAT.SRC]MISSING/UPDATE=(MASD\$: [EMULAT.ENH]MISS

0378 AH-BT13A-SE

# DIGITAL EQUIPMENT CORPORATION CONFIDENTIAL AND PROPRIETARY



0379 AH-BT13A-SE

## DIGITAL EQUIPMENT CORPORATION CONFIDENTIAL AND PROPRIETARY

